



Administration Guide

FortiFlex (Formerly Flex-VM) 25.4.1



FORTINET DOCUMENT LIBRARY

<https://docs.fortinet.com>

FORTINET VIDEO LIBRARY

<https://video.fortinet.com>

FORTINET BLOG

<https://blog.fortinet.com>

CUSTOMER SERVICE & SUPPORT

<https://support.fortinet.com>

FORTINET TRAINING & CERTIFICATION PROGRAM

<https://www.fortinet.com/training-certification>

FORTINET TRAINING INSTITUTE

<https://training.fortinet.com>

FORTIGUARD LABS

<https://www.fortiguard.com>

END USER LICENSE AGREEMENT

<https://www.fortinet.com/doc/legal/EULA.pdf>

FEEDBACK

Email: techdoc@fortinet.com



December 11, 2025

FortiFlex (Formerly Flex-VM) 25.4.1 Administration Guide

82-254-1179914-20251211

TABLE OF CONTENTS

Change Log	5
Introduction	6
FortiFlex v25.4.1 release information	7
New features and updates in v25.4.1	7
Getting started	8
Program requirements	8
Version and feature support	8
Registering FortiFlex	10
FortiFlex Portal	10
Accessing the portal	11
Adding a secondary user	11
Dashboard	11
Program guide	13
Program renewal	13
Points	14
Prepaid points	14
Postpaid points	15
Point calculation	15
Roll-Over points	15
Service offerings	16
Virtual Machines	16
Hardware Appliances	21
Cloud Services	22
Email notifications	28
Reports	28
Grace periods	30
Program Expiration	30
Negative Points	31
Deploying FortiFlex	32
Flex Entitlements	32
My Assets	34
Decommissioned units	34
Creating entitlements	35
Injecting the FortiFlex license	40
Confirming the license token is injected	45
Configuring web proxy tunneling for FDN	45
Managing Flex Entitlements	46
Creating a license pool group	51
Configurations	51
Creating configurations	52
Configuration details	57
Deployment examples and scripts	72
Manual deployment on KVM	72

Automatic deployments	79
Automation	80
FortiFlex API	80
FortiFlexVM Terraform provider	82
Ansible Collection	82
Tools	83
Points calculator	83
Daily points	85

Change Log

Date	Change Description
2025-12-06	Initial release.
2025-12-11	Updated Version and feature support on page 8 .

Introduction

FortiFlex allows you to easily manage usage entitlements. You can use the FortiFlex portal to create configurations, generate licensing tokens, and monitor resource consumption in the form of points.

FortiFlex provides a simplified and flexible licensing model for Fortinet products, including hardware, VM, and cloud services:

- VMs and associated services for core solutions, such as FortiGate, FortiManager, FortiAnalyzer, FortiWeb, and FortiADC
- FortiGate hardware services for multiple supported models
- SaaS and add-ons, such as FortiWeb Cloud, FortiGate Cloud, FortiSASE, and so on
- Endpoint security solutions, such as FortiClient EMS and FortiEDR Cloud

FortiFlex subscribers can create multiple sets of a single entitlement that corresponds to a licensed asset. Resource consumption is based upon predefined points that are calculated on a daily basis (PST/PDT time zone).

Configurations are reusable and can be modified as needed, affecting all entitlements using the given configuration. For example, a customer has a FortiGate-VM configuration with four vCPUs enabled and 10 FortiGate VMs entitled using said configuration. The customer then increases the number of vCPUs in the configuration to eight. Once the changes are applied and pushed to entitlements and licensing servers, the next time the 10 VMs perform a license and entitlement update against the servers, they will receive updated information and apply them locally to enable support to the increased number of vCPUs.

Virtual Machines with usage entitlements require a per-VM unique token to be installed on every VM. These tokens can be injected into the VM once the configurations and vCPU quantities are defined in the FortiFlex portal, and the VMs are deployed on the customer-managed platform in supported clouds and hypervisors.

See the [FortiFlex Concept Guide](#) for more information.

FortiFlex v25.4.1 release information

New features and updates in v25.4.1

FortiDeceptor Cloud

FortiDeceptor Cloud has been added as a Cloud Services offering. See [Configuration details on page 57](#) and [Service offerings on page 16](#).

FortiNAC Virtual Machine

FortiNAC Virtual Machine has been added as a Virtual Machine offering. See [Configuration details on page 57](#) and [Service offerings on page 16](#).

Getting started

Review the following content when getting started with FortiFlex:

- [Program requirements on page 8](#)
- [Registering FortiFlex on page 10](#)
- [FortiFlex Portal on page 10](#)

For more information, see the [Getting Started](#) guide.

Program requirements

The FortiFlex program requires the following items:

- A primary FortiCloud account or IAM user account.
- FortiFlex Program SKU (either Enterprise/prepaid or MSSP/postpaid) purchased from Fortinet's resellers and distributors.
- FortiFlex Point Pack SKU (only applicable to Enterprise/prepaid) purchased from Fortinet's resellers and distributors.

For more information, see the [Getting Started](#) guide.

Version and feature support

FortiFlex is supported in the following Fortinet solutions.

Product support

FortiFlex can be used to create usage entitlements for the following products:

- FortiGate-VM 6.4.3 and higher
- FortiWeb 7.0.1 and higher
- FortiManager 7.2.1 and higher
- FortiAnalyzer 7.2.2 and higher
- FortiPortal-VM 7.0.3 and higher
- FortiADC 7.4.0 and higher
- FortiClient EMS 7.2.2 and higher
- FortiWeb Cloud 23.3.a and higher
- FortiAP (All Software versions)
- FortiSwitch (All Software versions)
- FortiGate-HW (All Software versions)

- FortiSOAR-VM 7.6.1 and above
- FortiMail-VM 7.6.2 and above
- FortiNAC-VM 7.6.5 and above

Version support

FortiFlex licensed devices are supported in the physical and virtual versions of FortiManager and FortiAnalyzer.

- FortiManager 6.4.3 and higher
- FortiAnalyzer 6.4.3 and higher

VDOMs

FortiFlex natively supports VDOMs and no longer requires perpetual licenses.

FortiFlex supported VDOMs in the following products:

- FortiOS 6.4.9 and higher

VDOM limits

The following includes the maximum VDOM for the Service Bundle depending on the size of the VM:

VM size	Maximum VDOMs
VM01	10
VM02	25
VM04	50
VM08	500
VM16	500
VM32	500
VMUL	500

The following includes the maximum VDOM for the A La Carte Service depending on the size of the VM:

VM size	Maximum VDOMs
VM01	10
VM02 - VM03	25
VM04 - VM07	50
VM08+	500

FortiToken

FortiToken is supported on FortiFlex FortiGate-VMs.

Registering FortiFlex

FortiFlex is an annual or multi-year contracted program that can be registered through the FortiCloud Asset Management portal.

FortiFlex program-related SKUs are available for purchase from Fortinet's resellers and distributors. There may be certain conditions to be eligible to join the program. Consult your Fortinet sales representatives.

To register FortiFlex:

1. Log into your FortiCare account. The *Asset Management* portal opens.
2. Go to *Products > Product List*.
3. Click *Register More* and follow the steps in the registration wizard.
4. Log out of your account after the registration is complete.

For information about product registration, see [Registering products](#) in *Asset Management Administration Guide*.



The program begins on the date of registration. It may take up to four hours for the registration to validate in FortiCloud.

To access the FortiFlex portal:

1. Log in to your FortiCare account. The *Asset Management* portal opens.
2. In the banner, click *Services > Assets & Accounts > FortiFlex*.

To view your FortiFlex license:


1. Log into your FortiCare account. The *Asset Management* portal opens.
2. Click *Account Services*.

FortiFlex Portal

The FortiFlex portal allows you to monitor point consumption, configure entitlements, create licensing tokens, and run reports.

Accessing the portal

You can access the FortiFlex portal from the *Services* menu in Asset Management. The FortiFlex option appears in the *Asset & Accounts* section when there is a valid FortiFlex license.



Adding a secondary user


The FortiFlex portal supports the Master account in FortiCloud. To add secondary accounts, create an IAM user. For information, see [Adding IAM users](#).



The FortiFlex portal does not support FortiCloud sub user accounts. To grant access to a FortiCloud sub user, migrate the user in the IAM portal. See [Migrating sub users](#).

Dashboard

The *Dashboard* view provides an overview of activity in your FortiFlex account. Use the dashboard to quickly monitor active and expired virtual machines, as well points consumed.



The *Dashboard* contains the following monitors:

Monitor	Description
FortiFlex Program	Displays the program serial number and the program start and end dates.
Flex Entitlements Summary	Displays the number of <i>Active</i> , <i>Stopped</i> and <i>Expired</i> virtual machines.
Points Summary	For Prepaid programs, this field displays the <i>Total Remaining Points</i> and <i>Average Daily Point Usage for Past 30 Days</i>. For Postpaid and Evaluation programs, this field displays the <i>Current Period</i> month and a positive value for the <i>Total Consumed Points in the Period</i>.
Point Usage History for Past 30 Days	Displays the daily point usage for the past thirty days as a chart. Hover over a bar in the chart to see the points used for a specific day.

Program guide

The topics in this section provide information about the FortiFlex program.

- [Program renewal on page 13](#)
- [Points on page 14](#)
- [Service offerings on page 16](#)
- [Email notifications on page 28](#)
- [Reports on page 28](#)
- [Grace periods on page 30](#)

Program renewal

When you register a new FortiFlex contract for renewal, you have the option of selecting *Auto-extend VM configuration*.

ASSET MANAGEMENT

- Dashboard
- Products
- Online Renew
- Account Services

Register Product

Product Model: ELA VM Program Post Pay | Contract Number:

Important Notice:
READ BEFORE COMPLETING THE REGISTRATION.

PRODUCT ENTITLEMENT

SUPPORT TYPE	SUPPORT LEVEL	ACTIVATION DATE	EXPIRATION DATE
ELA VM Program	Web/Online	2022-06-30	2023-06-30

Entitlement calculation is based on any existing warranty or contract services plus the term of your new contract. If you have questions regarding these conditions, please open a ticket for Registration Assistance by clicking [here](#).

☒ Auto-extend VM configuration to new expiration date.

This tells FortiFlex to update the expiration date of all VM entitlements that have the *Termination Mode* set to *Follow Program*, to the expiration date of the new contract that is being registered.

Add VM Entitlement(s)

1 Details 2 Confirmation 3 Complete

1. VM Entitlement Details

Add VM Entitlement(s)

Product Type: *
FortiGate Virtual Machine - Service Bundle

Configuration: *
d877dcbb-9e46-4cb6-9775-ca2f8e1c4b6e

Number of Virtual Machine(s): *
1

Description:
My VMs

Termination Mode: *
☒ Follow Program
☐ User Defined

Program Expiration Date :
2024-05-26

Asset Folder: *
My Assets

< Cancel Next >

Points

Resource consumption is based upon predefined points that are calculated on a daily basis (PST/PDT time zone). Points can be purchased in advance or billed on a month basis based on the number of CPUs and service package.

Prepaid points

Prepaid points are available for Enterprise customers. Points are purchased in units of 1,000, 10,000, 50,000 and 100,000 points and are deducted on a daily basis based on resource consumption. Unused points can be rolled over upon the program registration anniversary date. See [Roll-over points](#).

One account can have only one Prepaid FortiFlex program. Multiple registrations can be performed to extend the existing program period.



FortiFlex Points can also be converted from FortiCloud FortiPoints in the Asset Management portal's *Marketplace*. This is only available for Prepaid programs at the root account level. See [FortiFlex](#) in the FortiCloud Asset Management guide.

New points can be registered at any time during the program contract as long as there is a valid, active FortiFlex prepaid program. If the FortiFlex program is expired, new points cannot be added and all unconsumed points are forfeited after 90 days following the expiration date.



For more information on available point packs, roll-over, and expiration, see the [FortiFlex Ordering Guide](#).

Grace Period for negative points

The negative points grace period is applicable only to Prepaid accounts and is activated whenever the points balances becomes negative. Customers have 90 days to bring the balance back to positive otherwise the account may be suspended.

Postpaid points

Points are calculated based on resource consumption and billed on a monthly basis. The detailed payment terms may be specified in your individual purchase agreements.

One account can have only one Postpaid FortiFlex program. Multiple registrations can be performed to extend the existing program period.



A FortiFlex account can only accommodate one prepaid program and one postpaid program at the same time.

Point calculation

Points are calculated daily based on PST/PDT time zones. Calculations are based on the number of CPUs and service package. You can change the per-VM entitlements as many time as you like in a day. The largest CPU size and service package for the day will be charged based on the PST/PDT time zone day count. It may take up to three hours for the change to be updated in FortiCloud.

Points are not calculated during a VM entitlement stoppage, even though the VM may still be running on the customer-managed environment.

Roll-Over points

Pre-paid points can be rolled-over on the service registration anniversary date. The full amount of unused points will be rolled over to the next year for stackable and bulk packs. Stackable packs will expire three years from the purchase date. Bulk packs will expire either three or five years from the purchase date.



Roll-over points do not apply to the post-paid program.



For more information on available point packs, roll-over, and expiration, see the [FortiFlex Ordering Guide](#).

Service offerings

The following table provides an overview of the available service packages:

- [Virtual Machines on page 16](#)
- [Hardware Appliances on page 21](#)
- [Cloud Services on page 22](#)

Virtual Machines

FortiGate Virtual Machine - Service Bundle

For detailed information, see the [FortiGate™ Virtual Appliances](#).

Bundles	Enterprise Protection	Unified Threat Protection	Advanced Threat Protection	FortiCare Only
FortiCare Premium	24x7	24x7	24x7	24x7
FortiGuard App Control Service	✓	✓	✓	✓
IPS	✓	✓	✓	
Application Control	✓	✓	✓	
Advanced Malware Protection	✓	✓	✓	
URL, DNS, & Video Filtering	✓	✓		
Anti-spam Service	✓	✓		
DLP	✓			
Inline CASB Database	✓			
AI-based Inline Malware Prevention	✓			
Attack Surface Security	✓			
Converter Service	✓			

Entitlement Limits				
vCPUS		VDOMs		
Minimum	1	VM01		10
Maximum	96	VM02 - VM03		25

Entitlement Limits			
Increments	1	VM04 - VM07	50
		VM08 - VM96	500

FortiGate Virtual Machine - A La Carte Services

The A La Carte Service package allows you to pick and choose the services you want use.

Service Type	Services
FortiGuard Services	Intrusion Prevention
	Advanced Malware Protection
	FortiGuard Attack Surface Security Service
	FortiGuard OT Security Service
	DLP
	AI-Based InLine Sandbox
	Web, DNS, & Video Filtering
	FortiConverter Service
Cloud Services	FortiGate Cloud
	SD-WAN Underlay
	FortiAnalyzer Cloud with SOCaaS
	FortiAnalyzer Cloud
	SD-WAN Connector for FortiSASE
Support Services	Cloud-based Overlay-as-a-Service
	FortiCare Premium
	FortiCare Elite

Entitlement Limits			
vCPUS		VDOMs	
Minimum	1	VM01	10
Maximum	96	VM02 - VM03	25
Increments	1	VM04 - VM07	50
		VM08 - VM96	500

FortiWeb Virtual Machine - Service Bundle

Service type	Advanced Bundle	Standard Bundle	Enterprise Bundle
FortiCare Premium + FortiWeb Security Service	✓	✓	✓
IP Reputation	✓	✓	✓
Antivirus	✓	✓	✓
FortiSandbox Cloud Service	✓		✓
Credential Stuffing Defense Service and Threat Analytics	✓		✓
Advanced Bot Protection			✓
Data Loss Prevention Service			✓
Client-Side Security Service			✓

FortiManager Virtual Machine

The FortiManager Virtual Machine allows you to set the number of managed devices and ADOMs.



FortiManager comes with a base of five ADOMs, per a default subscription. Therefore, the number of ADOMs is additional to this base. For example, if you add one ADOM in FortiFlex, the FortiManager VM is capable of six. See [Default and maximum number of ADOMs supported](#) in the FortiManager Release Notes.

Service Type		Included in bundle	
FortiCare Premium support		✓	

Entitlement Limits			
Devices		ADOMs	
Minimum	1	Minimum	0
Maximum	100 000	Maximum	100 000
Increments	1	Increments	1

FortiClient EMS On-Prem

Service Type	Services
Support Services	FortiCare Premium

Service Type	Services
Service Packages	FortiCare Best Practice
	ZTNA/VPN
	EPP/ATP + ZTNA/VPN
	Chromebook

Entitlement Limits	
All Endpoints	
Minimum	25
Maximum	85 000
Increments	1

FortiAnalyzer Virtual Machine

The FortiAnalyzer Virtual Machine allows you to set the daily storage (GB) and ADOMs.



FortiAnalyzer comes with a base of five ADOMs, per a default subscription. Therefore, the number of ADOMs is additional to this base. For example, if you add one ADOM in FortiFlex, the FortiAnalyzer VM is capable of six. See [Default and maximum number of ADOMs supported](#) in the FortiAnalyzer Release Notes.

Service Type	Included in bundle
FortiCare Premium support	✓
FortiGuard IOC (Indicators Of Compromise)	✓
Security Automation Service	✓
FortiGuard Outbreak Detection Service	✓

Entitlement Limits			
Storage (GB)		ADOMs	
Minimum	5	Minimum	0
Maximum	8 300	Maximum	1 200
Increments	1	Increments	1

FortiPortal Virtual Machine

Service Type		Included in bundle
FortiCare Premium support		✓
Entitlement Limits		
Devices		
Minimum	0	
Maximum	100 000	
Increments	1	

FortiADC Virtual Machine

Service Package	Included in bundle
FortiCare Premium	✓
Network Security	✓
Application Security	✓
AI Security	✓

FortiSOAR Virtual Machine

Entitlement Limits			
Prepaid and Postpaid		Evaluation	
Minimum	0 (disabled)	Minimum	0 (disabled)
Maximum	1 000	Maximum	5

FortiMail Virtual Machine

Entitlement Limits	
Quantity of entitlements per account	1
CPUs	
Minimum	1
Maximum	2

FortiNAC Virtual Machine

Entitlement Limits	
Minimum Quantity of Endpoints	25
Maximum Quantity of Endpoints	100,000
Increments	25
Evaluation Limits	
Minimum Quantity of Endpoints	25
Maximum Quantity of Endpoints	100
Increments	25

Hardware Appliances

FortiGate Hardware

The hardware device is purchased and owned by customers. However, only hardware that does not have any services already attached can be added to FortiFlex. If the hardware has any services attached, contact customer service to detach the services before configuring on FortiFlex.

The Continuous Service Policy is not applicable to FortiFlex entitlements.

Service Type	Services
Support Services	FortiCare Premium
	FortiCare Elite
	FortiCare Elite Upgrade
	ATP
	UTP
	Enterprise

The FortiCare Elite Upgrade can only be combined with one of the FortiGuard Service Bundles (ATP, UTP, or Enterprise).

FortiAP

Service Type	Services
Support Services	FortiCare Premium
	FortiCare Elite



The entitlement must be active for at least 30 days after creation.

FortiSwitch

Service Type	Services
Support Services	FortiCare Premium
	FortiCare Elite



The entitlement must be active for at least 30 days after creation.

Cloud Services

FortiWeb Cloud - Private

Service Type		Services	
Average Throughput		Average throughput measured by the 95th percentile.	
Web Applications		Number of web applications.	
Entitlement Limits			
Throughput		Web Apps	
Minimum	10	Minimum	1
Maximum	10 000	Maximum	5 000
Increments	25	Increments	1

FortiClient EMS Cloud

Service Type	Services
Support Services	FortiCare Best Practice
Service Packages	ZTNA/VPN
	ZTNA/VPN + FortiGuard Forensics
	EPP/ATP + ZTNA/VPN
	EPP/ATP + ZTNA/VPN + FortiGuard Forensics
	Chromebook

Entitlement Limits	
All Endpoints	
Minimum	25
Maximum	85 000
Increments	1

FortiSASE

Entitlement Limits					
Data Transfer		Branch On-Ramp Location		Additional Compute Region	
Minimum	0 (Disabled)	Minimum	0 (Disabled)	Minimum	2 (0 for Disabled)
Maximum	2 500 000	Maximum	2	Maximum	2
Increments	250	Increments	1	Increments	1

Evaluation Limits					
Data Transfer		Branch On-Ramp Location		Additional Compute Region	
Minimum	0 (Disabled)	Minimum	0 (Disabled)	Minimum	2 (0 for Disabled)
Maximum	1 000	Maximum	20	Maximum	16
Increments	250	Increments	1	Increments	1



The minimum entitlement term is 90 days after creation. Likewise, when editing an entitlement, the expiration date cannot be less than 90 days. For example, if an entitlement is *STOPPED* after 91 days and then reactivated, it cannot be *STOPPED* again for another 90 days.

FortiEDR MSSP

Service Type		Services	
Service Package		Discover/Protect/Respond	
Entitlement Limits			
Endpoints		Repository Storage	
Minimum	0	Minimum	0 (disabled)
Maximum	50 000	Maximum	30720 GB
Increments	1	Increments	512 GB
Evaluation Limits			
Repository Storage			
Minimum	0 (disabled)		
Maximum	512 GB		
Increments	512 GB		

FortiNDR Cloud

Entitlement Limits	
Minimum	1 Gbps
Maximum	10 000 Gbps
Increments	1
Evaluation Limits	
Minimum	1 Gbps
Maximum	5 Gbps
Increments	1

FortiRecon

Entitlement Limits	
Assets	
Minimum	200

Entitlement Limits	
Maximum	1 000 000
Increments	50
Networks	
Minimum	0 (Disabled)
Maximum	100
Increments	1
Executives	
Minimum	0 (Disabled)
Maximum	1 000
Increments	1
Vendors	
Minimum	0 (Disabled)
Maximum	1 000
Increments	1
Evaluation Limits	
Assets	
Minimum	1
Maximum	100
Increments	1
Networks	
Minimum	0 (Disabled)
Maximum	5
Increments	1
Executives	
Minimum	0 (Disabled)
Maximum	5
Increments	1
Vendors	
Minimum	0 (Disabled)
Maximum	5
Increments	1



Only one FortiRecon entitlement can be included in an account. However, two FortiRecon entitlements from different sources, such as a regular contract and FortiFlex, is allowed for migration.

FortiRecon entitlements must be active for at least 90 straight days. When creating a new entitlement, the expiration date cannot be less than 90 days from the date of creation. When editing an entitlement, the expiration date cannot be less than 90 days from the last date the entitlement was *ACTIVE*.

FortiSIEM Cloud

Entitlement Limits					
Compute Units		Online Storage		Archive Storage	
Minimum	10	Minimum	500 GB	Minimum	0 GB
Maximum	600	Maximum	60 000 GB	Maximum	60 000 GB
Increments	10	Increments	500 GB	Increments	500 GB

FortiDeceptor Cloud

Entitlement Limits	
Minimum Quantity of VLANs	2
Maximum Quantity of VLANs	1024
Increments	1

Evaluation Limits	
Minimum Quantity of VLANs	2
Maximum Quantity of VLANs	5
Increments	1

FortiAppSec

	Prepaid/Postpaid Limits	Evaluation Limits
Throughput		
Minimum	0	0
Maximum	10 Gbps	100
Increments	1	1

	Prepaid/Postpaid Limits	Evaluation Limits
Applications		
Minimum	0	0
Maximum	5 000	4
Increments	1	1
Queries Per Second		
Minimum	0	0
Maximum	1 000 000	100
Increments	1	1
Health Checks		
Minimum	0	0
Maximum	100 000	10
Increments	1	1



The values are not configurable in the FortiFlex portal. They are reported daily by the FortiAppSec Cloud controller.

FortiDLP

Endpoint Limits		
Minimum	25	
Maximum	100 000	
Increments	1	

FortiManager Cloud

	Prepaid/Postpaid Limits	Evaluation Limits
Quantity of Devices		
Minimum	3	3
Maximum	100 000	10
Increments	1	1

Email notifications

Email notifications are sent to provide updates on the current status of registered FortiFlex programs and points balances. When certain conditions are triggered, an email is sent by FortiFlex to notify you of the event that triggered the email. Emails are sent from noreply@fortinet.com.

Email notification types include:

Notification Type	Description
Low Balance	This email is used to notify users that the current point balance is less than the average consumption in the last 30 days multiplied by the number of days until it runs out. The email is triggered if the points balance is not high enough to maintain the current average points consumption for 90, 60, 30, 15, or seven days. This email is part of the Pre-paid program. For example, if the average points consumption in the last 30 days is 1000 points per day, FortiFlex will anticipate that the same average points consumption rate will be maintained for the next 90 days (1000 points per day * 90 days = 90 000 points consumed). However, if the current points balance is less than 90 000, FortiFlex will send an email alert to notify users that the points will run out in 90 days time.
Negative Balance	This email is used to notify users when the point balance becomes negative. This email is part of the Pre-paid program.
Program Anniversary	This email is used to mark how many days are left until the anniversary of program registration. The email is sent when there are 60, 30, 21, 15, seven, and three days left until the anniversary. This email is part of the Pre-paid program.
Program End	This email is used to notify users when the expiry of the program is approaching. The email is sent when there are 90, 60, 30, 21, 15, seven, and three days left until the program expires. This email is part of the Pre-paid and Post-paid programs.
Program Expired	This email is used to notify users about how many days have passed since the program expired. The email is sent when three, seven, 11, 15, 21, 26, and 30 days have passed since the program expired. This email is part of the Pre-paid and Post-paid programs.

Reports

The *Reports* tab contains the *Point Usage Summary*, *Point Usage Detail*, and *Point Pack Summary*. You can run a report for a specified time period, and then export it as a CSV, XLXS, or XML file.

To run the Point Usage Summary:

1. Go to *Reports > Point Usage Summary*.
2. Select the *Period* and *Account*. The *Consumed Points Breakdown* is displayed.

Period *		Account *
2024-02-01 - 2024-02-02		US\$0.00 / US\$0.00 / US\$0.00
Consumed Points Breakdown		
FortiGate Virtual Machine - Service Bundle	204.41 Points	
FortiManager Virtual Machine	1.97 Points	
FortiAnalyzer Virtual Machine	8.54 Points	
FortiADC Virtual Machine	32.40 Points	
FortiWeb Cloud - Private	83.32 Points	
FortiSASE	18.74 Points	
FortiEDR MSSP	0.96 Points	
Total Consumed Points:	350.54 Points	

- 3.** Select the product type. The breakdown of point usage for that product time in displayed.

FortiGate Virtual Machine - Service Bundle Consumed Points Breakdown		Period: 2024-02-01 - 2024-02-02	Back
Date	Product Type	Points	
2024-02-01	FortiGate Virtual Machine - Service Bundle	204.41	

- 4.** Select a date. The *Point Usage Detail* for that date is displayed.

Select Month

Start Date

02/01/2024

End Date

02/01/2024

Serial Number

Product Type

FortiGate Virtual Machine - Service Bundle

Account

Serial Number

Description

Configuration Name

Product Type

Usage Date

CPUs

Service Pack

VDOMs

FG_2_ATP

FortiGate Virtual Machine - Service Bundle

2024-02-01

2

ATP

0

FG_2_ATP

FortiGate Virtual Machine - Service Bundle

2024-02-01

2

ATP

0

FG_12_UTP

FortiGate Virtual Machine - Service Bundle

2024-02-01

12

UTP

15

FGT_9_ATP

FortiGate Virtual Machine - Service Bundle

2024-02-01

9

ATP+FGTDLDB+FG...

0

FGT_9_ATP

FortiGate Virtual Machine - Service Bundle

2024-02-01

9

ATP+FGTDLDB+FG...

0

FGT_9_ATP

FortiGate Virtual Machine - Service Bundle

2024-02-01

9

ATP+FGTDLDB+FG...

0

FG_Custom_UTP_12

FortiGate Virtual Machine - Service Bundle

2024-02-01

12

UTP+FGTSWNM

0

aaaa

FortiGate Virtual Machine - Service Bundle

2024-02-01

5

ENT+FGTDLDB+FG...

1

To run the Point Usage Detail Report:

1. Go to *Reports > Point Usage Detail*.
2. Select the desired filters.



The *Start Date* cannot be more than 90 days ago.

If FortiFlex is used in an Organization, the *OU/Account* dropdown menu will show options based on the user's permission scope. When in the root account, all accessible accounts will be displayed. When in a member account, only the current account will be displayed.

3. Click *View Report*. The report results are displayed.

Select Month

February 2024

Start Date

12/01/2023

End Date

02/02/2024

Serial Number

Product Type

FortiManager Virtual Machine

Account

View Report

4. (Optional) Right-click the report and click *Export* to download the report as a CSV or XLSX file.

To view the Point Pack Summary:

1. Go *Reports > Point Pack Summary*.

The FortiFlex point licenses that were registered are displayed. If there are no point packs registered, the report will be empty.

Point Pack Number	Point Amount	Used Amount	Remaining Amount	Registration Date	Expiration Date
	10000	10000	0	2023-08-16	2028-08-14
	10000	10030.1	-30.1	2024-01-09	N/A

2. (Optional) Right-click the report, and click *Export* to download the report as a CSV or XLSX file.

Grace periods

FortiFlex provides two types of 90-day grace periods, Program Expiration and Negative Points.

Program Expiration

This grace period is triggered when the FortiFlex program reaches the expiration date and it is applicable for both Prepaid and Postpaid programs.

During the Program Expiration grace period, all entitlements with *Termination Mode* set to *Follow Program* will have their FortiGuard expiration date set to 90 days after the original expiration date. This is to avoid service stoppage, allowing the user to renew the program to recover from the grace period.

It is important to highlight that during this period, the entitlement will still show as expired in the FortiCloud Asset Management portal, but internally FortiGuard will grant an extra 90 days on top. The extended expiration data will only be visible from within product’s UI or through CLI commands.

The Program Expiration grace period also plays a key role on the Prepaid program unused points. If the account has unused points, these points will be kept as valid in the account, as long as the program is renewed within the grace period but will be 100% forfeited if the grace period ends and program remains expired.

Negative Points

This grace period is only applicable to the Prepaid program, and it is triggered when the remaining points balance becomes negative.

FortiFlex allows points to be consumed as negative for up to 90 days and points true up will automatically happen whenever new points packs are added. When the points balance becomes positive again, then the FortiFlex program will leave the grace period. If the points balance remains negative after the grace period has ended, then all active entitlements will be stopped, and the user will be unable to use FortiFlex until the points balance becomes positive.

To buy additional points packs, please contact your Fortinet Inc. sales representative.



During any of the two grace periods, creating and updating entitlements is not allowed, and only existing active entitlements remain working. Points deduction will continue normally.



It is also possible that a given account hits both grace periods at the same time, where the user must fix both conditions in order to get the account out of the grace period restrictions.



If the FortiCloud account has the Asset Groups feature enabled, make sure to register the FortiFlex contract renewal under the same Asset Group and User Group where the FortiFlex service is registered to avoid the creation of a new FortiFlex SN, instead of renewing the existing one. See [Asset groups](#) in the FortiCloud Asset Management guide for more information.

Deploying FortiFlex

To deploy FortiFlex, create a configuration and use it to create a new entitlement. After the entitlement is created, inject the licensing token into the virtual machine. This will trigger the offering to download the corresponding license file.

To deploy FortiFlex:

1. [Creating configurations on page 52.](#)
2. [Creating entitlements on page 35.](#)
3. [Inject the FortiFlex license.](#)
4. [Monitor the points consumed.](#)
5. [Run reports to manage points and serial numbers.](#)

This section includes the following information:

- [Flex Entitlements on page 32](#)
- [Configurations on page 51](#)
- [Deployment examples and scripts on page 72](#)

Flex Entitlements

Use the *Flex Entitlements* page to create and manage license entitlements which are consumed via the license tokens. You can also disable compromised license entitlements or change the configuration.

You can change the entitlement scope by either editing the associated configuration or by migrating the token to another configuration. An entitlement can only be linked to a single configuration.



A License Token is a one-time code used to activate an instance. A new token must be re-generated if the instance needs to be re-activated. See [Managing Flex Entitlements on page 46](#).


FORTIFLEX ELA ELAVMR00 Prepare	VM Entitlements > My Assets						Search ...	?
	Total Records: 8						+ New VM Entitlement	
	Serial Number	License File Token	Configuration	Description	Termination Date	Status	Product Type	
	FGVMELTM20000...		FortiGate VM01		2020-09-16	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM02		2020-09-09	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM02		2021-09-08	EXPIRED	FortiGate-VM	
	FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM	

The table displays the following information:

Serial Number	The serial numbers generated when you configure an instance.
License File Token	The available License File Tokens that can be injected into a VM to leverage consumption entitlements.
Configuration	The VM configuration assigned to the serial number.
Description	The description of the entitlement you entered when the service was created.
Termination Date	The expiry date for the token. The token can be stopped, edited, or reactivated.
Status	The status of the entitlement. PENDING: The entitlement is created but not activated. The service is not being charged for daily consumption. ACTIVE: The entitlement is activated and the service is being charged for daily consumption (PST/PDT time zone). ACTIVE: The entitlement is in use. STOPPED: When the entitlement is stopped for the entire day, the VM will not be charged for the day. EXPIRED: The entitlement has exceeded the <i>Termination Date</i>. GRACE_PERIOD: The entitlement is <i>ACTIVE</i> but has a negative balance or a program expiration that has triggered the activation of the grace period. Once all grace period events have been cleared, it may take a full day for the status to change back from <i>GRACE_PERIOD</i> to <i>ACTIVE</i>.
 <i>PENDING, ACTIVE, and STOPPED</i> entitlements can be edited to update the <i>Configuration</i> and <i>Description</i>. <i>PENDING</i> and <i>ACTIVE</i> entitlements can also be edited to have a new <i>Termination Date</i>.	

My Assets

The My Assets view shows the Asset Folders assigned to an entitlement. You will only see the asset folders you have permission to view. Asset folders are created in the Asset Management portal. FortiFlex only shows services inside each folder except for when creating new services. For information about creating Asset Folders in Asset Management, see [Asset Management > Creating custom views](#).



Serial Number	License File Token	Configuration	Description	Termination Date	Status	Product Type
FGVMELTM20000...		FortiGate VM01		2020-09-16	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM02		2020-09-09	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM02		2021-09-08	EXPIRED	FortiGate-VM
FGVMELTM20000...		FortiGate VM01		2021-09-08	EXPIRED	FortiGate-VM

Asset folder permissions

Asset folder permissions are assigned in the Identity & Access Management (IAM) portal. For more information about Asset Folder permissions, see [Identity & Access Management \(IAM\) > Asset and portal permissions](#).




You can use an asset folder to request the next available serial number with the API. See [Creating a license pool group on page 51](#).

Decommissioned units

The *Decommissioned Units* view shows the serial numbers that were decommissioned in the Asset Management portal. When decommissioning an active serial number in the Asset Management portal, you must stop the entitlement before it can be decommissioned. Attempting to decommission the serial number while it is still active will return an error. See [Managing Flex Entitlements on page 46](#) for information on stopping entitlements.

For information about decommissioning units in Asset Management, see [Asset Management > Viewing decommissioned units](#).



Serial Number	License File Token	Configuration	Description	Termination Date	Status	Product Type
FGVMMLTM21006377		FortiGate 2CPUs		2021-11-16	STOPPED	FortiGate-VM

Creating entitlements

Entitlements can be created for virtual machines (VMs), hardware devices, and cloud services. The program requires a positive point balance to create entitlements.

This section includes:

- [Creating VM entitlements on page 35](#)
- [Creating hardware device entitlements on page 37](#)
- [Creating Cloud service entitlements on page 39](#)

Creating VM entitlements

Create a VM entitlement to be used with various VM products, including FortiGate-VM or FortiWeb-VM.



When you create a VM on FortiFlex the consumption for the VM starts when the entitlement is activated for the first time.

All newly created entitlements will be set to *PENDING* and will be changed to *ACTIVE* when the entitlement is activated by the VM instance, which triggers the start of charges.



You cannot add purchased VMs or pre-existing Trial or Evaluation services to FortiFlex. You must create a new VM entitlement.



Once the license entitlement becomes *ACTIVE*, it will remain active until:

- The expiration date is reached, or
- The user manually stops the entitlement through the FortiFlex UI or API.

FortiFlex does not monitor VM instance status, meaning it does not know if a VM instance is up or down, therefore it cannot automatically determine if a license entitlement should be active or stopped. It is the user's responsibility to manage the status of all license entitlements created in the FortiFlex platform.

To create a VM entitlement:

1. Go to *Flex Entitlements*, and click *New Flex Entitlement*. The *Add Flex Entitlement(s)* page opens.

1. Flex Entitlement Details

Add Flex Entitlement(s)

Product Type: *
Select Product Type

Configuration: *
Select Configuration

Number of Flex Entitlements: *
1

Termination Mode: *
☒ Follow Program
☐ User Defined

Asset Folder: *
My Assets

Program Expiration Date: 2029-08-15

☐ Skip PENDING status and activate the entitlement(s) immediately

< Cancel Next >

2. Configure the VM Entitlement.

Product Type	Select one of the following service bundles from the dropdown: • <i>FortiGate Virtual Machine - Service Bundle</i> • <i>FortiGate Virtual Machine - A La Carte Services</i> • <i>FortiWeb Virtual Machine - Service Bundle</i> • <i>FortiManager Virtual Machine</i> • <i>FortiClient EMS On-Prem</i> • <i>FortiAnalyzer Virtual Machine</i> • <i>FortiPortal Virtual Machine</i> • <i>FortiADC Virtual Machine</i> • <i>FortiSOAR Virtual Machine</i> • <i>FortiMail Virtual Machine</i> For information about the product types, see Service offerings on page 16 .
Configuration	Select a VM configuration from the list. See Creating a VM configuration on page 52 .
Number of Flex Entitlements	Enter the number of entitlements. See Creating a VM configuration on page 52 .
Description	Enter a description of the VM.
Termination Mode	• Select <i>Follow Program</i> to terminate the machine when the program expires. • Select <i>User Defined</i>, and select a date in the calendar to specify the termination date.
Asset Folder	Assign the VM to a folder in <i>My Assets</i> . For more information about Asset Folders, see Asset Management > Creating custom views .



You can use an asset folder to request the next available serial number with the API. See [Creating a license pool group on page 51](#).

Skip PENDING status and activate the entitlement(s) immediately

Select this option to immediately set your VM entitlement to *ACTIVE* instead of *PENDING* upon creation.

3. Click **Next**.
4. Review the *Flex Entitlement Details* and *Program Information*, and click **Submit**.

2. Confirmation

Flex Entitlement Details		Program Information	
Configuration:	FGT_9_ATP	Termination Mode:	Follow Program
Number of Flex Entitlements:	1	Program Expiration Date:	2029-08-15
Asset Folder:	My Assets		
Daily Points Consumption:	30.56		
Monthly Points Consumption:	916.80		

* Points consumption is calculated based on the Current Pricing.

< Cancel < Back Submit >

The *Serial Numbers(s)* are displayed.

3. Complete

SUCCESS!
Flex Entitlements created successfully.

Flex Entitlement Details		Program Information	
Configuration:	FGT_9_ATP	Termination Mode:	Follow Program
Number of Flex Entitlements:	1	Program Expiration Date:	2029-08-15
Asset Folder:	My Assets		

Serial Numbers	
1	FGVMELTM23091547

< List New Flex Entitlement >

Creating hardware device entitlements

Create a hardware device entitlement to be used with FortiGate products. License tokens are not applicable for hardware devices.

To create a hardware device entitlement:

1. Go to *Flex Entitlements*, and click *New Flex Entitlement*. The *Add Flex Entitlement(s)* page opens.

2. Configure the hardware entitlement.

Product Type

Select one of the following service bundles from the dropdown:

- *FortiGate Hardware*
- *FortiAP*
- *FortiSwitch*

For information about the product types, see [Service offerings on page 16](#).

Configuration

Select a configuration from the list. See [Creating a hardware appliance configuration on page 54](#).

Termination Mode

- Select *Follow Program* to terminate the machine when the program expires.
- Select *User Defined*, and select a date in the calendar to specify the termination date.

Serial Numbers

Enter the device serial numbers.

3. Click *Next*.
4. Review the *Flex Entitlement Details* and *Program Information*, and click *Submit*.

Points start to be consumed on the same day even though your managed hardware may still not be running.

Creating Cloud service entitlements

Create a Cloud service entitlement to be used with various products, including FortiWeb Cloud or FortiSASE. License tokens are not applicable for Cloud services.



You cannot add purchased Cloud services or pre-existing Trial or Evaluation services to FortiFlex. You must create a new Cloud service entitlement.

To create a Cloud service entitlement:

1. Go to *Flex Entitlements*, and click *New Flex Entitlement*. The *Add Flex Entitlement(s)* page opens.

2. Configure the Cloud entitlement.

Product Type

Select one of the following service bundles from the dropdown:

- FortiWeb Cloud
- FortiClient EMS Cloud
- FortiSASE
- FortiEDR MSSP
- FortiRecon
- FortiSIEM Cloud
- FortiNDR
- FortiAppSec
- FortiDLP
- FortiManager Cloud

For information about the product types, see [Service offerings on page 16](#).

Configuration

Select a configuration from the list. See [Creating a Cloud service configuration on page 56](#).

Number of Flex Entitlements

Enter the number of entitlements. See [Creating a Cloud service configuration on page 56](#).

Description

Enter a description.

Termination Mode

- Select *Follow Program* to terminate the machine when the program expires.
- Select *User Defined*, and select a date in the calendar to specify the termination date.

Asset FolderAssign the service to a folder in *My Assets*.

For more information about Asset Folders, see Asset Management > [Creating custom views](#).



You can use an asset folder to request the next available serial number with the API. See [Creating a license pool group on page 51](#).

3. Click *Next*.
4. Review the *Flex Entitlement Details* and *Program Information*, and click *Submit*.

2. Confirmation

Flex Entitlement Details	Program Information
Configuration: EMSCloud_01	Termination Mode: Follow Program
Number of Flex Entitlements: 1	Program Expiration Date: 2029-08-15
Asset Folder: My Assets	
Daily Points Consumption: 58.53	
Monthly Points Consumption: 1,755.90	

* Points consumption is calculated based on the Current Pricing.

<Cancel <Back Submit>

Injecting the FortiFlex license

Each FortiFlex entitlement has an associated license token that is automatically generated upon creation. To activate an entitlement, the license token must be injected into the target solution.

You can inject a FortiFlex license into a VM instance via the CLI or during the VM bootstrapping via Cloud-Init (KVM) or OVF template (ESXi).



The commands `vm-license-options count` and `vm-license-options interval` allow for the customization of license token activation retry parameters. See [VM license](#) in the FortiOS Administration Guide for more information.

Requisites:


- [Create the VM configuration](#)

Injecting the FortiFlex license consists of the following steps:

1. Ensure that the VM has Internet connectivity properly configured.
2. Inject the FortiFlex License Token into the VM using one of the following methods:
 - [CLI](#)
 - [OVF Template \(FGT-64VM only\)](#)
 - [Cloud-init](#)
 - [FortiOS API](#)
3. [Confirm that the license token is injected](#)
4. [Configuring web proxy tunneling for FDN](#)



Review specific product documentation information for more information on license token injection in the [Fortinet Document Library](#).

FortiFlex License Activation Workflow

Inject a FortiFlex license with the CLI

For general virtual machine targets, such as FortiGate VM, the token can be inject with the execute `vm-license` command.

To inject a FortiFlex license with the FortiFlex CLI:

To inject a FortiFlex license into a VM instance with the CLI:

```
execute vm-license <license_token>
```

Example:

```
exec vm-license 58923569A3FFB7F46879
```

To inject a FortiFlex license via web proxy:

```
execute vm-license <license_token> <proxy>
```

The following are examples of the syntax for <proxy>:

```
http://user:password@proxyip:proxyport  
user:password@proxyip:proxyport
```

The following shows examples for each command:

```
exec vm-license 58923569A3FFB7F46879 http://qa:123456@10.1.100.74:8080  
exec vm-license 95D87F50C075C6F20EE7 hazel:123456@10.1.100.74:8080
```

Inject a license token with an OVF template

The custom OVF template contains a *License Token* and *Configuration URL* fields where a bootstrap configuration for the FortiGate is stored.



This option is only available for VMware vCenter.

To inject a license token with a custom OVF template:

1. Create a new FGT-VM64 from the vCenter web UI with the extracted files in *FGT_VM64-v7-buildxxxx-FORTINET.out.ovf.zip*.
2. Deploy an OVF Template.

3. In the *Customize template* step:

- a. Enter the License Token in the *License Token* field.
- b. Enter the Configuration URL in the *Configuration URL* field.

Deploy OVF Template

- 1 Select an OVF template
- 2 Select a name and folder
- 3 Select a compute resource
- 4 Review details
- 5 License agreements
- 6 Configuration
- 7 Select storage
- 8 Select networks
- 9 Customize template
- 10 Ready to complete

Customize template ✕

Fortigate 6 settings	
License Token	182C8C8143C841028572
Configuration URL	http://172.18.64.219/fgt-174
Hostname	FortiGate-VM
Primary DNS	208.91.112.53
Secondary DNS	208.91.112.52
FortiManager	FQDN or IP address of FortiManager

Interface 01 4 settings	
Interface 1: Mode	IP/Netmask will be ignored if DHCP is chosen. Static
IP	10.6.30.66
Netmask	255.255.255.0
Gateway	10.6.30.254

CANCEL
BACK
NEXT

4. Restart the VM instance.

After the FGT-VM64 is started, it will activate VM license and load the configuration automatically

```

FortiGate-VM64.vapp-ip66 - VMware Remote Console
VMRC | [Icons]
Loading flatkc... ok
Loading /rootfs.gz...ok
Decompressing Linux... Parsing ELF... done.
Booting the kernel.

System is starting...
Serial number is FGUMMLTM20000045

FortiGate-VM login: *ATTENTION*: Admin sessions removed because license registra
tion status changed to 'VALID'
  
```

Inject a FortiFlex license via cloud-init

The following are the MIME files that you can use to inject a FortiFlex license into a FortiGate-VM instance using cloud-init. See [cloud-init Documentation](#) for details.



FortiGate-VMs can be deployed into Proxmox using cloud-init and a FortiFlex token. See the [Proxmox Administration Guide](#) for more information.

Configuration information for the FortiGate-VM

```
Content-Type: multipart/mixed; boundary="=====0740947994048919689=="
MIME-Version: 1.0
-----0740947994048919689==
Content-Type: text/plain; charset="us-ascii"
MIME-Version: 1.0
Content-Transfer-Encoding: 7bit
Content-Disposition: attachment; filename="config"
config sys glo
set hostname FGT-MSSP-MIME
set admintimeout 480
end
.....
```

License token information

```
-----0740947994048919689==
Content-Type: text/plain; charset="us-ascii"
MIME-Version: 1.0
Content-Transfer-Encoding: 7bit
Content-Disposition: attachment; filename="license"
LICENSE-TOKEN:FF69500C90C1604F71EE
-----0740947994048919689---
```

Injecting with the FortiOS API

The FortiOS API method is useful for automating the migration of existing FortiGate-VM instances into FortiFlex. The FortiFlex API and documentation are available on the [Fortinet Developer Network](#) website.

Example: Inject a license via HTTP method:

```
<user_email>:~# curl -k --request POST 'http://<IP_
address>/api/v2/monitor/system/vmlicense/download?token=<token_ID>&access_token=<access_token>'
{
  "http_method": "POST",
  "status": "success",
  "http_status": 200,
  "vdom": "root",
  "path": "system",
```

```
"name": "vmlicense",
"action": "download",
"serial": "<serial_number>",
"version": "v7.2.0",
"build": 1157
```

Example: Inject a license via proxy URL:

```
<user_email>:~# curl -k --request POST 'https://<IP_
address>/api/v2/monitor/system/vmlicense/download?token=<token_ID>&proxy_url=<proxy_URL>&access_
token=<token>'
{
  "http_method": "POST",
  "status": "success",
  "http_status": 200,
  "vdom": "root",
  "path": "system",
  "name": "vmlicense",
  "action": "download",
  "serial": "<serial_number>",
  "version": "v7.2.0",
  "build": 1157
}<user_email>:~#
```

Confirming the license token is injected

To confirm that the license token is injected:

```
diagnose debug cloudinit show
>> Checking metadata source ovf
>> Found metadata source: ovf
>> Trying to install vmlicense ...
>> License-token:95D87F50C075C6F20EE7 http://qa:123456@10.1.100.74:8080
>> Config script is not available

get system status
Version: FortiGate-VM64 v7.0.4,buidl0292,220115 (interim)
Serial-Number: FGVMLTM111111
```

Configuring web proxy tunneling for FDN

After the FortiFlex license has been installed, the FortiGate-VM must validate the license on FDN servers. You can also configure a proxy to accomplish this.

To configure web proxy tunneling for FDN:

```
config system autoupdate tunneling
  set status enable
  set address "<web proxy IP address or FQDN>"
```

```
set port <web proxy port>
set username "<username>"
set password <password>
end
```

It may take a while for FortiGate-VM to be able to validate the VM license and update UTP signatures from FortiGuard.

The following shows the output from `get system status` when the FortiGate-VM has completed the validation and update:

```
Version: FortiGate-VM64 v7.0.4,build0292,220115 (interim)
Virus-DB: 89.08825(2022-01-18 21:26)
Extended DB: 89.08825(2022-01-18 21:26)
Extreme DB: 1.00000(2018-04-09 18:07)
AV AI/ML Model: 2.04168(2022-01-18 18:45)
IPS-DB: 6.00741(2015-12-01 02:30)
IPS-ETDB: 19.00243(2022-01-18 01:30)
APP-DB: 19.00243(2022-01-18 01:30)
INDUSTRIAL-DB: 19.00243(2022-01-18 01:30)
IPS Malicious URL Database: 3.00246(2022-01-18 20:50)
Serial-Number: FGVMMLTM111111
License Status: Valid
License Expiration Date: 2022-10-31
VM Resources: 1 CPU/2 allowed, 2007 MB RAM
Log hard disk: Available
Hostname: FGT-DEMO
Private Encryption: Disable
Operation Mode: NAT
Current virtual domain: root
Max number of virtual domains: 1
Virtual domains status: 1 in NAT mode, 0 in TP mode
Virtual domain configuration: disable
FIPS-CC mode: disable
Current HA mode: standalone
Branch point: 0292
Release Version Information: interim
FortiOS x86-64: Yes
System time: Tue Jan 18 21:46:36 2022
Last reboot reason: warm reboot
```

Managing Flex Entitlements

You can stop and regenerate a license token if it is stolen or compromised. After the token is regenerated, it must be re-injected into your VM to revoke the old token. You can also export a list of tokens to parse them in scripts.

Modifying FortiGate-VM configurations

We recommend rebooting the FortiGate-VM after you change the configuration. To verify the configuration is in effect, run the following CLI command:

```
get system status
```

- A reboot is required if you are lowering the vCPU size.
- A reboot is recommended when adding more vCPU.

If you do not want to reboot the VM, run the following CLI command:

```
exec cpu add X
```

Where X is the number of vCPU to be hot-added on top of the existing number.




Starting in FortiOS 7.2.4, vCPU changes in the FortiFlex licenses are automatically handled by the FortiGate-VM instances. Running `exec cpu add X` is no longer required if you are running FortiOS v7.2.4.

Managing entitlements

To stop a VM Entitlement:

1. Go to *Flex Entitlements*, and click the serial number you want to stop.
2. Click *Stop*. The *Stop VM Entitlement* dialog opens.

3. Click *Confirm*. The VM status changes to *STOPPED*. Point consumption will stop from the next day even while your managed VM may be still running.



To stop multiple VM entitlements:

1. Go to *Flex Entitlements*.
2. Select the entitlements you want to stop. The *Stop* button is displayed.



You can only perform bulk entitlement actions for serial numbers that are the same product type. Use the column filters to filter for a specific product *Serial Number* or *Product Type*.

Total Records: 88

Stop New Flex Entitlement

SERIAL NUMBER	LICENSE FILE TOKEN	CONFIGURATION	PRODUCT TYPE	DESCRIPTION	STATUS	TERMINATION DATE
☐ FGVMELTM		FG_8_UTP	FortiGate-VM		EXPIRED	2024-03-27
☒ FGVMELTM		Alacarte_02	FortiGate-VM	Sample	ACTIVE	2029-12-12
☐ FGVMELTM		FG_8_UTP	FortiGate-VM		EXPIRED	2024-04-04
☐ FGVMELTM		FG_16_ENT	FortiGate-VM		PENDING	2024-04-08
☐ FGVMELTM		FG_2_ATP	FortiGate-VM		STOPPED	2024-04-04

3. Click *Stop*. A confirmation message is displayed.
4. Click *Confirm*.

To reactivate a VM Entitlement:

1. Go to *Flex Entitlements* and click a serial number with a status of *STOPPED*.
2. Click *Reactivate*. The *Virtual Machine Details* page opens.

3. (Optional) Modify the VM Entitlement details.

4. Click *Submit*. The serial number *Status* changes to *Active*. Point consumption will restart from the day you make this change even though you may still have not rerun your managed VM.

To reactivate multiple VM entitlements:

1. Go to *Flex Entitlements*.
2. Select the entitlements you want to reactivate. The *Reactivate* button is displayed.



You can only perform bulk entitlement actions for serial numbers that are the same product type. Use the column filters to filter for a specific product *Serial Number* or *Product Type*.

Total Records: 88

[Reactivate](#) [New Flex Entitlement](#)

SERIAL NUMBER #	LICENSE FILE TOKEN #	CONFIGURATION #	PRODUCT TYPE #	DESCRIPTION #	STATUS #	TERMINATION DATE #
☐ FGVMELTM		FG_8_UTP	FortiGate-VM		EXPIRED	2024-03-27
☐ FGVMELTM		Alacarte_02	FortiGate-VM	Sample	ACTIVE	2029-12-12
☒ FGVMELTM		FG_8_UTP	FortiGate-VM		EXPIRED	2024-04-04
☐ FGVMELTM		FG_16_ENT	FortiGate-VM		PENDING	2024-04-08
☐ FGVMELTM		FG_2_ATP	FortiGate-VM		STOPPED	2024-04-04
☐ FGVMELTM		FG_2_ATP	FortiGate-VM		STOPPED	2024-04-04
☐ FGVMELTM		FG_2_ATP	FortiGate-VM		PENDING	2023-10-25
☐ FGVMELTM		FG_2_ATP	FortiGate-VM		ACTIVE	2029-12-12
☒ FGVMELTM		FG_2_ATP	FortiGate-VM		EXPIRED	2024-04-04

3. Click *Reactivate*. A confirmation message is displayed.

4. Select the *Termination Mode*.



If you select User Defined, select the Program the *Expiration Date*.

Reactivate Flex Entitlement

Are you sure you want to reactivate 2 Flex Entitlements?

Termination Mode: *

☒ Follow Program

☐ User Defined

Program Expiration Date : 2029-12-12

[Close](#) [Confirm](#)

5. Click *Confirm*.

To export a list of serial numbers and tokens:

1. Go to *Flex Entitlements*.
2. Right-click the table, and click *Export*.
3. Select *CSV Export*, *Excel Export (xlsx)*, or *Excel Export (.xml)*. The file is saved to your computer.

VM Entitlements > FortiGate

Search ...

Total Records: 7

[ADD NEW](#)

Serial Number	License File Token	Configuration	Description	Termination Date	Status
		FortiGate		2022-06-10	ACTIVE
		FortiGate		2022-06-10	ACTIVE
		FortiGate		2022-06-10	ACTIVE
		FortiGate			STOPPED
		FortiGate			EXPIRED
		FortiGate 2CPUs			ACTIVE
		FortiGate 2CPUs		2021-11-16	STOPPED

Context menu options: Copy, Copy with Headers, Paste, Export, CSV Export, Excel Export (xlsx), Excel Export (xml)

Creating a license pool group

A license pool group allows you to request the next available serial number in the pool. When a VM is decommissioned, the license is returned to the pool.

Requirements:

- Access to Asset Management
- Fortinet Developer Network membership

To create a license pool group:

1. In Asset Management, create an Asset Folder for the asset pool group. See [Creating custom views](#).
2. Create a VM Entitlement and select a folder for the group. See, [Creating entitlements on page 35](#).
3. Use the [Virtual Machines](#) API to create and add a folderpath to the asset folder in My Assets.
4. Create a new endpoint to return the group information.
5. Create a new endpoint to return the next available token.


Configurations

The *Configurations* tab is used to create and manage configurations. Configurations are used to define a template for entitlement creation and consumption. It defines the product form factor and type, the capacity or sizing, and associated service packages.

You can create and modify configurations as required, while also being able to examine its details, associated entitlements, and history. A configuration can be linked to multiple entitlements at once. The scope defined by a configuration applies to all entitlements using that configuration. Any changes to a configuration affect all entitlements tied to that configuration.

Configurations can be in two states: active or disabled. Entitlements using a disabled configuration are not able to consume points. However, disabled configurations can be reactivated.

See [Creating configurations on page 52](#).



The screenshot shows the 'Configurations' tab in the FortiFlex interface. At the top, there's a header bar with 'Configurations' on the left, a search bar, and a 'New Configuration' button. Below the header, it says 'Total Records: 43' and 'Show Disabled Configurations' with a toggle switch. The main content is a table with three columns: 'CONFIGURATION #', 'PRODUCT TYPE #', and 'STATUS #'. The table lists several configurations, all with a status of 'ACTIVE'.

CONFIGURATION #	PRODUCT TYPE #	STATUS #
FW_01	FortiWeb-VM	ACTIVE
FMG_01	FortiManager-VM	ACTIVE
EMS_OnPerm_02	FortiClient-EMS	ACTIVE
FP_01	FortiPortal-VM	ACTIVE
FADC_01	FortiADC-VM	ACTIVE
FWC_Private_01	FortiWeb-Cloud	ACTIVE
Test_FMG_ChangeConfig_With_Very_Long_Name_For_Testing_Trim_Funct...	FortiManager-VM	ACTIVE
eeafesd	FortiManager-VM	ACTIVE

When you disable a configuration, the entitlements that are using the configuration are no longer entitled to consume points. Use caution when disabling configurations or stopping entitlements, as this will impact the

performance of the virtual machines, devices, or services. Disabled configurations can be re-enabled. Enabled *Show Disabled Configurations* to include disabled configurations in the Configurations list.

Configurations		
Total Records: 69		Show Disabled Configurations ☐
+ New Configuration		
CONFIGURATION #	PRODUCT TYPE #	STATUS #
FW_01	FortiWeb-VM	ACTIVE
FMG_01	FortiManager-VM	ACTIVE
EMS_OnPerm_01	FortiClient-EMS	DISABLED
EMS_OnPerm_02	FortiClient-EMS	ACTIVE
FP_01	FortiPortal-VM	ACTIVE
FADC_01	FortiADC-VM	ACTIVE
FWC_Private_01	FortiWeb-Cloud	ACTIVE
Test_FMG_ChangeConfig_With_Very_Long_Name_For_Testing_Trim_Funct...	FortiManager-VM	ACTIVE
eaefsd	FortiManager-VM	ACTIVE
fafdasgad	FortiManager-VM	DISABLED
test_002_Update	FortiManager-VM	DISABLED

Creating configurations

Create configurations to be used in VM, hardware device, and cloud service entitlements.

This section includes:

- [Creating a VM configuration on page 52](#)
- [Creating a hardware appliance configuration on page 54](#)
- [Creating a Cloud service configuration on page 56](#)

Creating a VM configuration

Specify the number of vCPUs and service package to use in a VM entitlement. See [Creating VM entitlements on page 35](#).

To create a VM configuration:

1. Go to *Configurations*, and click *New Configuration*.
2. In the *Configuration Details* page, set the configuration details and click *Next*.

Name

Enter a configuration name.



The configuration name is a label and not the identifier of the configuration. Changes to the name do not affect any references to the given configuration, which is referred to by its configuration ID. However, you cannot have two configurations with the same name.

Form Factor

Virtual Machines

Product Type

Select one of the following options:

- *FortiGate Virtual Machine - Service Bundle*

- *FortiGate Virtual Machine - A La Carte Services*
- *FortiWeb Virtual Machine - Service Bundle*
- *FortiManager Virtual Machine*
- *FortiClient EMS On-Prem*
- *FortiAnalyzer Virtual Machine*
- *FortiPortal Virtual Machine*
- *FortiADC Virtual Machine*
- *FortiSOAR Virtual Machine*
- *FortiMail Virtual Machine*

For information, see [Service offerings on page 16](#).

1. Configuration Details

Set Configuration Details

Name *

Select Product

Form Factor *

Virtual Machines

Hardware Appliances

Cloud Services

Product Type *

FortiGate Virtual Machine - Service Bundle

FortiGate Virtual Machine - A La Carte Services

FortiWeb Virtual Machine - Service Bundle

FortiManager Virtual Machine

FortiClient EMS On-Prem

FortiAnalyzer Virtual Machine

FortiPortal Virtual Machine

FortiADC Virtual Machine

Cancel Next >

3. In the *Configuration Setup* page, set the service details and click *Next*. For more information, see [Configuration details on page 57](#).

2. Configuration Setup

Set Configuration Values

Number of CPUs *

Service Package *

Virtual Domains

0

Cancel < Back Next >

- Review the configuration details, and click *Submit*.

3. Review Configuration

Configuration Details		FortiGate Virtual Machine - Service Bundle	
Name:	FGT VM	Number of CPUs:	2 CPUs
Program Serial Number:	FEXVM	Service Package:	Enterprise
		Virtual Domains:	1

Cancel < Back Submit >

- Click *List* to view the configuration in the *Configurations* tab.

4. Complete

⊙ SUCCESS!
Configuration created successfully.

Configuration Details		FortiGate Virtual Machine - Service Bundle	
Name:	FGT VM	Number of CPUs:	2 CPUs
Status:	ACTIVE	Service Package:	Enterprise
Program Serial Number:	FEXVM	Virtual Domains:	1

List New Configuration

Creating a hardware appliance configuration

Specify the device model and service package to use in a hardware device entitlement. See [Creating hardware device entitlements on page 37](#).

To create a hardware appliance configuration:

- Go to *Configurations*, and click *New Configuration*.
- In the *Configuration Details* page, set the configuration details and click *Next*.

Name	Enter a configuration name.  The configuration name is a label and not the identifier of the configuration. Changes to the name do not affect any references to the given configuration, which is referred to by its configuration ID. However, you cannot have two configurations with the same name.
Form Factor	Hardware Appliances
Product Type	Select the following option: - FortiGate Hardware - FortiAP - FortiSwitch For information, see Service offerings on page 16 .

1. Configuration Details

Set Configuration Details

Name *

Enter Configuration Name

Select Product

Form Factor *

Virtual Machines

Hardware Appliances

Cloud Services

Product Type *

FortiGate Hardware

FortiAP

FortiSwitch

Cancel

Next >

3. In the *Configuration Setup* page, set the service details and click *Next*. For more information, see [Configuration details on page 57](#).

2. Configuration Setup

Set Configuration Values

Device Model *

Service Package *

Addons

☐ FortiCare Elite Upgrade

☐ FortiGate Cloud Management

☐ AI-Based In-line Sandbox

☐ SD-WAN Underlay

☐ FortiGuard DLP

☐ FortiAnalyzer Cloud

☐ SOCsaaS

☐ Managed FortiGate

☐ SD-WAN Connector for FortiSASE

☐ FortiConverter Service

Cancel

< Back

Next >

4. Review the configuration details, and click *Submit*.

3. Review Configuration

Configuration Details		FortiGate Hardware	
Name:	Test	Device Model:	FortiGate-40F
Program Serial Number:	ELAVM	Service Package:	ATP
		Addons:	None

Cancel

< Back

Submit >

5. Click *List* to view the configuration in the *Configurations* tab.

4. Complete

🟢 SUCCESS!
Configuration created successfully.

Configuration Details		FortiGate Hardware	
Name:	Test	Device Model:	FortiGate-40F
Status:	ACTIVE	Service Package:	ATP
Program Serial Number:	ELAVM	Addons:	None

List

New Configuration

Creating a Cloud service configuration

Specify the users, endpoints, service package, and bandwidth for a Cloud service entitlement. See [Creating Cloud service entitlements on page 39](#).

To create a Cloud service configuration:

1. Go to *Configurations*, and click *New Configuration*.
2. In the *Configuration Details* page, set the configuration details and click *Next*.

Name	Enter a configuration name.  The configuration name is a label and not the identifier of the configuration. Changes to the name do not affect any references to the given configuration, which is referred to by its configuration ID. However, you cannot have two configurations with the same name.
Form Factor	Cloud Services
Product Type	Select one of the following options: • FortiWeb Cloud • FortiClient EMS Cloud • FortiSASE • FortiEDR MSSP • FortiRecon • FortiSIEM Cloud • FortiNDR • FortiAppSec For information, see Service offerings on page 16 .

3. In the *Configuration Setup* page, set the service details and click *Next*. For more information, see [Configuration details on page 57](#).

2. Configuration Setup

Set Configuration Values

ZTNA/VPN (number of endpoints) *

0

ZTNA/VPN + FortiGuard Forensics (number of endpoints) *

0

EPP/ATP + ZTNA/VPN (number of endpoints) *

0

EPP/ATP + ZTNA/VPN + FortiGuard Forensics (number of endpoints) *

0

Chromebook (number of endpoints) *

0

Addons

☐ FortiCare Best Practice

Cancel < Back Next >

4. Review the configuration details, and click *Submit*.

3. Review Configuration

Configuration Details		FortiClient EMS Cloud	
Name:	Test Cloud	ZTNA/VPN (number of endpoints):	25
Program Serial Number:	ELAVM: [REDACTED]	ZTNA/VPN + FortiGuard Forensics (number of endpoints):	25
		EPP/ATP + ZTNA/VPN (number of endpoints):	25
		EPP/ATP + ZTNA/VPN + FortiGuard Forensics (number of endpoints):	0
		Chromebook (number of endpoints):	0
		Addons:	None

Cancel < Back Submit >

5. Click *List* to view the configuration in the *Configurations* tab.

4. Complete

🟢 SUCCESS!
Configuration created successfully.

Configuration Details		FortiClient EMS Cloud	
Name:	Test Cloud	ZTNA/VPN (number of endpoints):	25
Status:	ACTIVE	ZTNA/VPN + FortiGuard Forensics (number of endpoints):	25
Program Serial Number:	ELAVM: [REDACTED]	EPP/ATP + ZTNA/VPN (number of endpoints):	25
		EPP/ATP + ZTNA/VPN + FortiGuard Forensics (number of endpoints):	0
		Chromebook (number of endpoints):	0
		Addons:	None

List New Configuration

Configuration details

This topic includes configuration details of the following:

- Virtual Machines on page 57
- Hardware Appliances on page 62
- Cloud Services on page 69

Virtual Machines

FortiGate Virtual Machine - Service Bundle

Number of CPUs	Enter the number of CPUs.
Service Package	Select one of the following options: • <i>FortiCare Premium</i> • <i>UTP</i> • <i>Enterprise</i> • <i>ATP</i>

Virtual Domains	Enter the number of virtual domains.
FortiGuard Services	Select from the following options: • <i>Advanced Malware Protection</i> • <i>AI-Based In-line Sandbox</i> • <i>FortiGuard OT Security Service</i> • <i>FortiGuard DLP</i> • <i>FortiGuard Attack Surface Security Service</i> • <i>FortiConverter Service</i>
Cloud Services	Select from the following options: • <i>FortiGate Cloud Management</i> • <i>SD-WAN Underlay</i> • <i>SOCaaS</i> • <i>FortiAnalyzer Cloud</i> • <i>Cloud-based Overlay-as-a-Service</i> • <i>SD-WAN Connector for FortiSASE</i>
Support Services	Select one of the following options: • <i>FC Elite Upgrade</i>
Number of Flex Entitlements	Enter the number of FortiFlex entitlements.

FortiGate Virtual Machine - A La Carte Services

Number of CPUs	Enter the number of CPUs.
FortiGuard Services	Select from the following options: • <i>Intrusion Prevention</i> • <i>Advanced Malware Protection</i> • <i>FortiGuard Attack Surface Security Service</i> • <i>FortiGuard OT Security Service</i> • <i>DLP</i> • <i>AI-Based InLine Sandbox</i> • <i>Web, DNS & Video Filtering</i> • <i>FortiConverter Service</i>
Cloud Services	Select from the following options: • <i>FortiGate Cloud</i> • <i>SD-WAN Underlay</i> • <i>FortiAnalyzer Cloud with SOCaaS</i> • <i>FortiAnalyzer Cloud</i> • <i>SD-WAN Connector for FortiSASE</i> • <i>Cloud-based Overlay-as-a-Service</i>
Support Services	Select one of the following options: • <i>FortiCare Premium</i> • <i>FortiCare Elite</i>
Virtual Domains	Enter the number of Virtual Domains.



The FortiGate VM will report two Virtual Domains (VDOMs) due to its native ability to create an admin VDOM. The number of VDOMs added in FortiFlex is in addition to these two VDOMs. For example, if you add one VDOM in FortiFlex, the VM will report three VDOMs.

Number of Flex Entitlements Enter the number of FortiFlex entitlements.

FortiWeb Virtual Machine - Service Bundle

Number of CPUs Select the number of CPUs from the dropdown.

Service Package Select the service package:

- *Standard*
- *Advanced*
- *Enterprise*

Number of Flex Entitlements Enter the number of FortiFlex entitlements.

FortiManager Virtual Machine

Number of managed devices Enter the number of managed devices.

Number of ADOMs Enter the number of ADOMs.



FortiManager comes with a base of five ADOMs, per a default subscription. Therefore, the number of ADOMs is additional to this base. For example, if you add one ADOM in FortiFlex, the FortiManager VM is capable of six.

Number of Flex Entitlements Enter the number of FortiFlex entitlements.



After creating an entitlement which contains any of the Cloud Services, you can refer to the following on-boarding guides for further instructions:

- [FortiGate Cloud](#)
- [FortiManager Cloud](#)
- [FortiAnalyzer Cloud](#)

FortiClient EMS On-Prem

ZTNA/VPN Enter the number of endpoints.

EPP/ATP + ZTNA/VPN Enter the number of endpoints.

Chromebook Enter the number of endpoints.

Support Services Select a support service:

- *FortiCare Premium*

Addons	Select an add on: • <i>FortiCare Best Practice</i>
---------------	--

Number of Flex Entitlements	Enter the number of FortiFlex entitlements.
------------------------------------	---

FortiAnalyzer Virtual Machine

Daily Storage (GB)	Use the toggle to set the select the number of GB of daily storage.
---------------------------	---

Number of ADOMs	Use the toggle to set the select the number of ADOMS.
------------------------	---



FortiAnalyzer comes with a base of five ADOMs, per a default subscription. Therefore, the number of ADOMs is additional to this base. For example, if you add one ADOM in FortiFlex, the FortiAnalyzer VM is capable of six.

Support Services	Select a support service: • <i>FortiCare Premium</i>
-------------------------	--

Addons	Select an add on: • <i>OT Security Service</i> • <i>Attack Surface Security Surface</i> • <i>FortiAI Service</i>
---------------	--

Number of Flex Entitlements	Enter the number of FortiFlex entitlements.
------------------------------------	---



FortiAnalyzer comes with IOC, the Security Automation Service, and the FortiGuard Outbreak Detection Service. These additional services cannot be detached or purchased a-la-carte.

FortiPortal Virtual Machine

Number of managed devices	Use the toggle to set the select the number of managed devices.
----------------------------------	---

Number of Flex Entitlements	Enter the number of FortiFlex entitlements.
------------------------------------	---

FortiADC Virtual Machine

Number of CPUs	Select the number of CPUs from the dropdown.
-----------------------	--

Service Package	Select the service package from the dropdown: • <i>FortiCare Premium</i> • <i>Network Security</i> • <i>Application Security</i> • <i>AI Security</i>
------------------------	--

Number of Flex Entitlements	Enter the number of FortiFlex entitlements.
------------------------------------	---

FortiSOAR Virtual Machine

Service Package	Select the service package from the dropdown: • <i>Enterprise Edition</i> • <i>Multi Tenant Edition - Manager</i> • <i>Multi Tenant Edition - Tenant Node - Single User</i> • <i>Multi Tenant Edition - Tenant Node - Multi User</i>
Additional Users License	Enter the number of additional user licenses.
Add ons	Select an add on: • <i>Threat Intelligence Management</i>  <i>This option is unavailable if the service package is Multi Tenant Edition - Tenant Node - Single User.</i>

FortiMail Virtual Machine

Number of CPUs	Select the number of CPUs from the dropdown.
Service Package	Select the service package from the dropdown: • <i>Base Bundle</i> • <i>ATP Bundle</i>
Add ons	Select an add on: • <i>Advanced Management</i> • <i>Dynamic Content Analysis</i> • <i>Cloud Email API Integration</i> • <i>Email Continuity</i>  Add ons are disabled if only one CPU is selected.

FortiNAC Virtual Machine

Service Package	Select the service package from the dropdown: • <i>Plus</i> • <i>Pro</i>
Number of Endpoints	Enter the number of endpoints.
Support Services	Select a support service: • <i>FortiCare Premium</i>



FortiFlex is supported on FortiNAC VM 7.6.5 or later.

Hardware Appliances

FortiGate Hardware

Device Model

Select one of the device models from the dropdown:

- *FortiWifi-30E*
- *FortiWifi-40F*
- *FortiWifi-40F-3G4G*
- *FortiWifi-50E*
- *FortiWifi-50E-2R*
- *FortiWifi-51E*
- *FortiWifi-50G-DSL*
- *FortiWifi-50G-SFP*
- *FortiWifi-60E*
- *FortiWifi-60E-DSL*
- *FortiWifi-60E-DSLJ*
- *FortiWifi-60F*
- *FortiWifi-61E*
- *FortiWifi-61F*
- *FortiWifi-80F-2R*
- *FortiWifi-80F-2R-3G4G-DSL*
- *FortiWifi-81F-2R*
- *FortiWifi-81F-2R-3G4G-DSL*
- *FortiWifi-81F-2R-3G4G-PoE*
- *FortiWifi-81F-2R-POE*
- *FortiGateRugged-35D*
- *FortiGateRugged-60F*
- *FortiGateRugged-60F-3G4G*
- *FortiGateRugged-70F*
- *FortiGateRugged-70F-3G4G*
- *FortiGate-30E*
- *FortiGate-30E-3G4G-GBL*
- *FortiGate-30G*
- *FortiGate-40F*
- *FortiGate-40F-3G4G*
- *FortiGate-50E*
- *FortiGate-50G*

- *FortiGate-50G-DSL*
- *FortiGate-50G-SFP*
- *FortiGate-50G-SFP-PoE*
- *FortiGate-51E*
- *FortiGate-51G*
- *FortiGate-51G-5G*
- *FortiGate-51G-SFP-PoE*
- *FortiGate-60E*
- *FortiGate-60E-DSL*
- *FortiGate-60E-DSLJ*
- *FortiGate-60E-POE*
- *FortiGate-60F*
- *FortiGate-61E*
- *FortiGate-61F*
- *FortiGate-70F*
- *FortiGate-70G*
- *FortiGate-71F*
- *FortiGate-71G*
- *FortiGate-80E*
- *FortiGate-80E-POE*
- *FortiGate-80F*
- *FortiGate-80F-PoE*
- *FortiGate-80F-Bypass*
- *FortiGate-80F-DSL*
- *FortiGate-81E*
- *FortiGate-81E-POE*
- *FortiGate-81F*
- *FortiGate-81F-PoE*
- *FortiGate-90E*
- *FortiGate-90G*
- *FortiGate-91E*
- *FortiGate-91G*
- *FortiGate-100E*
- *FortiGate-100EF*
- *FortiGate-100F*
- *FortiGate-101E*
- *FortiGate-101F*
- *FortiGate-120G*
- *FortiGate-121G*
- *FortiGate-140E-POE*
- *FortiGate-200E*

- *FortiGate-200F*
- *FortiGate-200G*
- *FortiGate-201E*
- *FortiGate-201F*
- *FortiGate-201G*
- *FortiGate-300E*
- *FortiGate-301E*
- *FortiGate-400E*
- *FortiGate-400E-BYPASS*
- *FortiGate-400F*
- *FortiGate-401E*
- *FortiGate-401E-DC*
- *FortiGate-401F*
- *FortiGate-500E*
- *FortiGate-501E*
- *FortiGate-600E*
- *FortiGate-600F*
- *FortiGate-601E*
- *FortiGate-601F*
- *FortiGate-900G*
- *FortiGate-900G-DC*
- *FortiGate-901G*
- *FortiGate-901G-DC*
- *FortiGate-1000F*
- *FortiGate-1001F*
- *FortiGate-1100E*
- *FortiGate-1100E-DC*
- *FortiGate-1101E*
- *FortiGate-1800F*
- *FortiGate-1800F-DC*
- *FortiGate-1801F*
- *FortiGate-1801F-DC*
- *FortiGate-2000E*
- *FortiGate-2200E*
- *FortiGate-2201E*
- *FortiGate-2500E*
- *FortiGate-2600F*
- *FortiGate-2600F-DC*
- *FortiGate-2601F*
- *FortiGate-2601F-DC*
- *FortiGate-3000F*

- *FortiGate-3000F-DC*
- *FortiGate-3001F*
- *FortiGate-3001F0DC*
- *FortiGate-3200F*
- *FortiGate-3201F*
- *FortiGate-3300E*
- *FortiGate-3301E*
- *FortiGate-3400E*
- *FortiGate-3400E-DC*
- *FortiGate-3500F*
- *FortiGate-3501F*
- *FortiGate-3600E*
- *FortiGate-3600E-DC*
- *FortiGate-3601E*
- *FortiGate-3700F*
- *FortiGate-3701F*
- *FortiGate-3960E*
- *FortiGate-3960E-DC*
- *FortiGate-3980E*
- *FortiGate-3980E-DC*
- *FortiGate-4200F*
- *FortiGate-4200F-DC*
- *FortiGate-4400F*
- *FortiGate-4400F-DC*
- *FortiGate-4401F*
- *FortiGate-4800F*
- *FortiGate-4800F-DC*
- *FortiGate-4801F*
- *FortiGate-4801F-DC*
- *FortiGate-6001F*

Service Package

Select one of the following options:

- *FortiCare Essential*
- *FortiCare Premium*
- *FortiCare Elite*
- *ATP*
- *UTP*
- *Enterprise*

Addons

Select an add on:

- *FortiCare Elite Upgrade*
- *FortiGate Cloud Management*
- *AI-Based In-line Sandbox*

- *SD-WAN Underlay*
- *FortiGuard DLP*
- *FortiAnalyzer Cloud*
- *SOCaaS*
- *Managed FortiGate*
- *SD-WAN Connector for FortiSASE*
- *FortiConverter Service*
- *FortiGuard OT Security Service*
- *SD-WAN Overlay-as-a-Service*
- *Advanced Malware Protection*
- *Intrusion Prevention*
- *Attack Surface Security Service*
- *Web, DNS & Video Filtering*
- *FortiSASE Subscription*

Number of Flex Entitlements Enter the number of FortiFlex entitlements.

Additional FPC modules Increase or decrease the quantity of FPC modules.



This option is available when the *Device Model* is set to FortiGate 6001F.



Hardware entitlements cannot be applied to a hardware FortiGate with an active license. You must either:

- Wait for the FortiGate to expire and then apply the FortiFlex license. There is a 48-hour grace period after the license expires where security subscriptions and FortiGuard will continue to work.
- Request Customer Service to de-register the device. This option does not grant the 48-hour grace period. Once it is de-registered, the FortiGate will be unable to receive security updates or utilize FortiGuard services.

FortiAP

Device Model Select one of the device models from the dropdown:

- *FortiAP-23JF*
- *FortiAP-221E*
- *FortiAP-222E*
- *FortiAP-223E*
- *FortiAP-224E*
- *FortiAP-231E*
- *FortiAP-231F*
- *FortiAP-231G*
- *FortiAP-233G*

- *FortiAP-234F*
- *FortiAP-234G*
- *FortiAP-431F*
- *FortiAP-431G*
- *FortiAP-432F*
- *FortiAP-432FR*
- *FortiAP-432G*
- *FortiAP-433F*
- *FortiAP-433G*
- *FortiAP-441K*
- *FortiAP-443K*
- *FortiAP-831F*
- *FortiAP-U231F*
- *FortiAP-U234F*
- *FortiAP-U422EV*
- *FortiAP-U431F*
- *FortiAP-U432F*
- *FortiAP-U433F*

Service Package

Select one of the following options:

- *FortiCare Premium*
- *FortiCare Elite*

Addons

Select an add on:

- *FortiSASE Cloud Managed AP*

FortiSwitch**Device Model**

Select one of the device models from the dropdown:

- *FortiSwitch-108E*
- *FortiSwitch-108E-FPOE*
- *FortiSwitch-108E-POE*
- *FortiSwitch-108F*
- *FortiSwitch-108F-FPOE*
- *FortiSwitch-108F-POE*
- *FortiSwitch-110G-FPOE*
- *FortiSwitch-124E*
- *FortiSwitch-124E-FPOE*
- *FortiSwitch-124E-POE*
- *FortiSwitch-124F*
- *FortiSwitch-124F-FPOE*
- *FortiSwitch-124F-POE*
- *FortiSwitch-148E*
- *FortiSwitch-148E-POE*

- *FortiSwitch-148F*
- *FortiSwitch-148F-FPOE*
- *FortiSwitch-148F-POE*
- *FortiSwitch-224D-FPOE*
- *FortiSwitch-224E*
- *FortiSwitch-224E-POE*
- *FortiSwitch-248D*
- *FortiSwitch-248E-FPOE*
- *FortiSwitch-248E-POE*
- *FortiSwitch-424D*
- *FortiSwitch-424D-FPOE*
- *FortiSwitch-424D-POE*
- *FortiSwitch-424E*
- *FortiSwitch-424E-FPOE*
- *FortiSwitch-424E-Fiber*
- *FortiSwitch-424E-POE*
- *FortiSwitch-448D*
- *FortiSwitch-448D-POE*
- *FortiSwitch-448E*
- *FortiSwitch-448E-FPOE*
- *FortiSwitch-448E-POE*
- *FortiSwitch-524D*
- *FortiSwitch-524D-FPOE*
- *FortiSwitch-548D*
- *FortiSwitch-548D-FPOE*
- *FortiSwitch-624F*
- *FortiSwitch-624F-FPOE*
- *FortiSwitch-648F*
- *FortiSwitch-648F-FPOE*
- *FortiSwitch-1024D*
- *FortiSwitch-1024E*
- *FortiSwitch-1048D*
- *FortiSwitch-1048E*
- *FortiSwitch-2048F*
- *FortiSwitch-3032D*
- *FortiSwitch-3032E*
- *FortiSwitch-M426E-FPOE*
- *FortiSwitch-T1024E*
- *FortiSwitchRugged-112D-POE*
- *FortiSwitchRugged-124D*
- *FortiSwitchRugged-216F-POE*

	• <i>FortiSwitchRugged-424F-POE</i>
Service Package	Select one of the following options: • <i>FortiCare Premium</i> • <i>FortiCare Elite</i>

Cloud Services

FortiWeb Cloud - Private

Average Throughput	Select average throughput measured by the 95th percentile from the dropdown, between 10 Mbps to 10 Gbps.
Web Applications	Enter the number of web applications, between 1 and 5000.

FortiClient EMS Cloud

ZTNA/VPN	Enter the number of endpoints.
ZTNA/VPN + FortiGuard Forensics	Enter the number of endpoints.
EPP/ATP + ZTNA/VPN	Enter the number of endpoints.
EPP/ATP + ZTNA/VPN + FortiGuard Forensics	Enter the number of endpoints.
Chromebook	Enter the number of endpoints.
Addons	Select an add on: • <i>FortiCare Best Practice</i>
Number of Flex Entitlements	Enter the number of FortiFlex entitlements.

FortiSASE

Number of users	Enter the number of users.
Service Package	Select a service package: • <i>Standard</i> • <i>Advanced</i> • <i>Comprehensive</i>
Data Transfer	Enter data transfer allowance required.
Dedicated Public IP	Enter the number of dedicated public IP addresses.
Branch On-Ramp Locations - Fortinet Cloud	Enter the number of locations.

Branch On-Ramp Locations - Public Cloud

Enter the number of locations.

Available only for the *Comprehensive* service package.**Global Region**

Select to enable.

Additional Compute Region - Fortinet Cloud

Enter the number of regions.

Additional Compute Region - Public Cloud

Enter the number of regions.

Available only for the *Comprehensive* service package.

Scaling down is not supported for:

- *Branch On-Ramp Locations - Fortinet Cloud*
- *Branch On-Ramp Locations - Public Cloud*
- *Additional Compute Region - Fortinet Cloud*
- *Additional Compute Region - Public Cloud*

FortiEDR MSSP**Service Package**

Select a service package:

- *Discover/Protect/Respond*

Repository Storage

Enter the amount of required storage in GB.

Addons

Select an add on:

- *XDR*



The number of EDR and XDR endpoints will be the same when creating a configuration.

FortiNDR Cloud

FortiNDR cannot be custom configured in the FortiFlex portal. When configuring a FortiNDR offering, the *Set Configuration Values* page will be bypassed. Metered Usage is controlled by FortiNDR Cloud.

FortiRecon**Service Package**

Select a service package:

- *External Attack Surface Monitoring*

	• <i>External Attack Surface Monitoring & Brand Protect</i> • <i>External Attack Surface Monitoring & Brand Protect & Adversary Centric Intelligence</i>
Number of Monitored Assets	Enter the number of monitored assets.
Internal Attack Surface Monitoring	Enter the number of networks.
Additional Executive Monitoring	Enter the number of executives.
Additional Vendor Monitoring	Enter the number of vendors.

FortiSIEM Cloud

Number of Compute Units	Enter the number of compute units.
Additional Online Storage	Enter the amount of additional online storage.
Archive Storage	Enter the amount of archive storage.
Region	Select the region of the instance as <i>Region A</i> or <i>Region B</i> .



You cannot scale down *Additional Online Storage* and *Archive Storage*.

FortiDeceptor Cloud

Service Package	Select the service package: • <i>Premium Bundle</i>
Number of VLANs	Enter the amount of VLANs.

FortiAppSec

Service Type	Select the service types: • <i>Cloud WAF</i> • <i>Cloud GSLB</i>
Cloud WAF Service Package	Select a service package: • <i>Standard</i> • <i>Advanced</i> • <i>Enterprise</i>
Cloud WAF Add-ons	SOCaaS



Cloud WAF Service Package and Cloud WAF Add-ons are only available if Cloud WAF has been selected as a service type.

FortiDLP

Service Package

Select a service package:

- *Standard (Endpoint DLP)*
- *Enterprise (Endpoint DLP and Insider Risk Management)*
- *Enterprise Premium (Endpoint DLP, Insider Risk Management, and premium PoP hosting location)*

Number of Endpoints

Enter the number of endpoints.

Addons

Select an add-on:

- *Best Practice Service*



If the *Best Practice Service* add-on is selected, it cannot be disabled for 90 days.

FortiManager Cloud

Number of Devices

Enter the number of devices.

Addons

Select an add-on:

- *FortiAI Service*

Deployment examples and scripts

The following section provides an example of a manual deployment for KVM as well as links to sample scripts to automate deployments for KVM.

- [Manual deployment on KVM on page 72](#)
- [Automatic deployments on page 79](#)

Manual deployment on KVM

Activate a FortiGate VM using a FortiFlex license. FortiFlex allows for adhoc license via its portal.

Step 1. Create the FortiFlex configuration.

To create a FortiFlex configuration:

1. Open the FortiFlex portal.
2. Go to *Configurations* and click *New configuration*.
3. In the *Configuration Details* page, enter a name for the configuration and the product type and click *Next*.

1. Configuration Details

Set Configuration Details

Name *

Select Product

Form Factor *

Virtual Machines

Hardware Appliances

Cloud Services

Product Type *

FortiGate Virtual Machine - Service Bundle

FortiGate Virtual Machine - A La Carte Services

FortiWeb Virtual Machine - Service Bundle

FortiManager Virtual Machine

FortiClient EMS On-Prem

FortiAnalyzer Virtual Machine

FortiPortal Virtual Machine

FortiADC Virtual Machine

Cancel Next >

4. Set the configuration values and click *Next*.

2. Configuration Setup

Set Configuration Values

Number of CPUs *

Service Package *

Virtual Domains

0

Cancel < Back Next >

5. On the *Review configuration* page, click *Submit*.

3. Review Configuration

Configuration Details		FortiGate Virtual Machine - Service Bundle	
Name:	FGT VM	Number of CPUs:	2 CPUs
Program Serial Number:	FEKVM	Service Package:	Enterprise
		Virtual Domains:	1

Cancel < Back Submit >

The configuration is complete.

4. Complete

🟢 SUCCESS!
Configuration created successfully.

Configuration Details		FortiGate Virtual Machine - Service Bundle	
Name:	FGT VM	Number of CPUs:	2 CPUs
Status:	ACTIVE	Service Package:	Enterprise
Program Serial Number:	FEXVM [REDACTED]	Virtual Domains:	1

List [New Configuration](#)

Step 2. Create the license entitlement

To create a license entitlement:

1. Go to *VM Entitlements* and click *New VM Entitlement*.
2. In the *VM Entitlement Details* page, from the *Configuration* list, select the configuration you created in Step 1 and click *Next*.

1. VM Entitlement Details

Add VM Entitlement(s)

Product Type: *
FortiGate Virtual Machine

Configuration: *
Demo_Config

Number of Virtual Machine(s): *
1

Description:
FortiGate for Demo

Termination Mode: *
☐ Follow Program
☒ User Defined

Expiration Date: *
04 / 04 / 2022

Asset Folder: *
My Assets

< Cancel [Next >](#)

3. On the *Confirmation* page, click *Submit*.

2. Confirmation

VM Entitlement Details		Program Information	
Configuration:	Demo_Config	Termination Mode:	User Defined
Number of Virtual Machine(s):	1	Program Expiration Date:	2022-04-04
Description:	FortiGate for Demo		
Asset Folder:	MyAssets		
Daily Points Consumption:	2.42		
Monthly Points Consumption:	72.60		

[< Cancel](#)
[< Back](#)
[Submit](#)

The license entitlement is created. The serial number is displayed under *Generated Serial Number(s)*.

3. Complete

✔ **SUCCESS !**
VM Entitlement(s) created successfully.

VM Entitlement Details		Program Information	
Configuration:	Demo_Config	Termination Mode:	User Defined
Number of Virtual Machine(s):	1	Program Expiration Date:	2022-04-04
Description:	FortiGate for Demo		
Asset Folder:	MyAssets		
Generated Serial Number(s)			
1	FGVMMLTM22000608		

[< List](#)
[New VM Entitlement](#)

4. Go to *VM Entitlements* and search for the Serial Number you generated. Click the Serial Number to view the Product details.

Total Records: 150 + New VM Entitlement

Serial Number ⓘ	License File Token ⓘ	Configuration ⓘ	Description ⓘ	Termination Date ⓘ	Status ⓘ	ProductType ⓘ
FGVMMLTM22000482	FL7974BLC33FFU/8F3AY7	96c2262f-af87-4129-99a8-...	NSX Acert	2022-05-27	ACTIVE	FortiGate VM
FGVMMLTM22000483	73893C9515BC7C1C3FE6	96c2262f-af87-4129-99a8-...	NSXT_Acert	2022-05-27	ACTIVE	FortiGate VM
FGVMMLTM22000518	81E79D7206F6948237D7	Intel		2022-03-17	EXPIRED	FortiGate VM
FGVMMLTM22000519	D7F4086A3A7F507AAC94	Intel		2022-03-17	EXPIRED	FortiGate VM
FGVMMLTM22000520	9A4E746155D520A8ABEA	EDR_Config		2022-03-17	EXPIRED	FortiGate VM
FGVMMLTM22000521	E66EBB596ACA650F370F	EDR_Config		2022-03-17	EXPIRED	FortiGate VM
FGVMMLTM22000564	CFAB469D787F8C41C487	2-CPU5	tes	2022-03-31	EXPIRED	FortiGate VM
FGVMMLTM22000565	DA5564FC91711AB5920E	new_2vCPU		2022-03-31	EXPIRED	FortiGate VM
FGVMMLTM22000577	8FBCCC16B35E2CEF7A48	Vinod_config	cvvxcvxc	2022-03-30	EXPIRED	FortiGate VM
FGVMMLTM22000578	FB12DD7F2E907BA89A4	new_2vCPU	dddd	2022-03-31	EXPIRED	FortiGate VM
FGVMMLTM22000579	DC961B0073D6DFFBEEBB	new_2vCPU	dddd	2022-03-31	EXPIRED	FortiGate VM
FGVMMLTM22000588	6D5C08EFF94F25384900	122414a8-ee19-41a8-8b41...	FGT-122414a8-ee19-41a8-...	2022-04-01	EXPIRED	FortiGate VM
FWBVMMLTM22000042	D9AC81E40C0F70198C4D	FWB_CFG		2022-03-31	STOPPED	FortiWeb-VM
FWBVMMLTM22000043	ADD472F591BB7835D1BA	FWB_2CPUS	dddd	2022-04-03	ACTIVE	FortiWeb-VM
FGVMMLTM22000607	9902ED2C98FD0C7747FC	FGT_Config_Demo	FortiGate-VM for Demo	2022-04-04	ACTIVE	FortiGate VM
FGVMMLTM22000608	1C778333E2962B0E0F8F	Demo_Config	FortiGate for Demo	2022-04-04	ACTIVE	FortiGate VM

5. In the *Details* page, copy the *License File Token*. You will need this token to activate the FortiGate VM instance.

Details
Points

Back
Edit
Stop

VM Entitlement Details
Token Details

Configuration: Demo_Config
Status: ACTIVE
Description: FortiGate for Demo
Start Date: 2022-04-02
Termination Date: 2022-04-04

License File Token: 1C778333E2962B0E0F8F
Regenerate


FortiFlex (Formerly Flex-VM) 25.4.1 Administration Guide
Fortinet Inc.

76

Step 3: Configure the VM

To configure the VM:

1. Open the KVM host which has already deployed the FortiGate VM and connect to it.


A terminal window titled 'root@sd-kvm:/var/lib/libvirt/images/flex' showing the process of connecting to a FortiGate VM. The user enters 'virsh console fgt-flex' and is prompted for a login. The login is successful with 'admin' as the username.

```
[root@sd-kvm flex]# virsh console fgt-flex
Connected to domain fgt-flex
Escape character is ^]

FortiGate-VM64-KVM login: admin
Password:
Welcome!

FortiGate-VM64-KVM #
```

2. Confirm the VM is connected to the Internet.

A terminal window showing the execution of a ping command to google.com. The output shows successful ping results with 0% packet loss and round-trip times around 59.7-59.8 ms.

```
[root@sd-kvm flex]# virsh console fgt-flex
Connected to domain fgt-flex
Escape character is ^]

FortiGate-VM64-KVM login: admin
Password:
Welcome!

FortiGate-VM64-KVM # execute ping www.google.com
PING www.google.com (172.253.63.103): 56 data bytes
64 bytes from 172.253.63.103: icmp_seq=0 ttl=102 time=59.8 ms
64 bytes from 172.253.63.103: icmp_seq=1 ttl=102 time=59.7 ms
64 bytes from 172.253.63.103: icmp_seq=2 ttl=102 time=59.8 ms
64 bytes from 172.253.63.103: icmp_seq=3 ttl=102 time=59.7 ms
64 bytes from 172.253.63.103: icmp_seq=4 ttl=102 time=59.7 ms

--- www.google.com ping statistics ---
5 packets transmitted, 5 packets received, 0% packet loss
round-trip min/avg/max = 59.7/59.7/59.8 ms

FortiGate-VM64-KVM #
```

3. Activate the license with the following command:

```
execute vm-license <license_token>
```

```

Mansee VM Entitlement - FGVMMLTM22000608
root@sd-kvm:/var/lib/libvirt/images/flex

[root@sd-kvm flex]# virsh console fgt-flex
Connected to domain fgt-flex
Escape character is ^]

FortiGate-VM64-KVM login: admin
Password:
Welcome!

FortiGate-VM64-KVM # execute ping www.google.com
PING www.google.com (172.253.63.103): 56 data bytes
64 bytes from 172.253.63.103: icmp_seq=0 ttl=102 time=59.8 ms
64 bytes from 172.253.63.103: icmp_seq=1 ttl=102 time=59.7 ms
64 bytes from 172.253.63.103: icmp_seq=2 ttl=102 time=59.8 ms
64 bytes from 172.253.63.103: icmp_seq=3 ttl=102 time=59.7 ms
64 bytes from 172.253.63.103: icmp_seq=4 ttl=102 time=59.7 ms

--- www.google.com ping statistics ---
5 packets transmitted, 5 packets received, 0% packet loss
round-trip min/avg/max = 59.7/59.7/59.8 ms

FortiGate-VM64-KVM # execute vm-license 1C778333E2962B0E0F8F

```

4. When prompted enter y to allow the VM to reboot to activate the new license. The VM reboots and the license is validated against the FortiGaurd servers.

```

64 bytes from 172.253.63.103: icmp_seq=2 ttl=102 time=59.8 ms
64 bytes from 172.253.63.103: icmp_seq=3 ttl=102 time=59.7 ms
64 bytes from 172.253.63.103: icmp_seq=4 ttl=102 time=59.7 ms

--- www.google.com ping statistics ---
5 packets transmitted, 5 packets received, 0% packet loss
round-trip min/avg/max = 59.7/59.7/59.8 ms

FortiGate-VM64-KVM # execute vm-license 1C778333E2962B0E0F8F
This operation will reboot the system !
Do you want to continue? (y/n)y

Requesting FortiCare license token: *****, proxy:(null)
VM license install succeeded. Rebooting firewall.

FGVMMLTM22000608 login:

The system is going down NOW !!

Please stand by while rebooting the system.
Restarting system.

System is starting...
The config file may contain errors.
Please see details by the command 'diagnose debug config-error-log read'.
Serial number is FGVMMLTM22000608

FGVMMLTM22000608 login:

```

5. To confirm the license and configuration, run the following command:
get system status

```
root@sd-kvm:/var/lib/libvirt/images/flex
FGVMM22000608 login: admin
Password:
Welcome!

FGVMM22000608 # get system status
Version: FortiGate-VM64-KVM v7.2.0,build1157,220331 (GA.F)
Virus-DB: 1.00000(2018-04-09 18:07)
Extended DB: 1.00000(2018-04-09 18:07)
Extreme DB: 1.00000(2018-04-09 18:07)
AV AI/ML Model: 0.00000(2001-01-01 00:00)
IPS-DB: 6.00741(2015-12-01 02:30)
IPS-ETDB: 6.00741(2015-12-01 02:30)
APP-DB: 6.00741(2015-12-01 02:30)
INDUSTRIAL-DB: 6.00741(2015-12-01 02:30)
IPS Malicious URL Database: 1.00001(2015-01-01 01:01)
IoT-Detect: 0.00000(2001-01-01 00:00)
Serial-Number: FGVMM22000608
License Status: Valid
License Expiration Date: 2022-04-07
VM Resources: 2 CPU/2 allowed, 2007 MB RAM
Log hard disk: Not available
Hostname: FGVMM22000608
Private Encryption: Disable
Operation Mode: NAT
Current virtual domain: root
Max number of virtual domains: 2
Virtual domains status: 1 in NAT mode, 0 in TP mode
Virtual domain configuration: disable
FIPS-CC mode: disable
--More--
```

Automatic deployments

Customers with access to Orchestrator tools can use the FortiFlex API to automate the FortiGate deployment and activation.

Automatic deployment on KVM

Automate the FortiGate deployment and activation on HyperVisor using a python script and the KVM cloud-init capabilities.

A Python script with examples of the basic calls for the FortiFlex API is available in the [Fortinet Developer Network](#) (FNDN). To view the script, log in to FNDN and search for the following article: *Sample Python Script for Flex-VM API*.

Automation

The topics in this section provide information about automation and the FortiFlex API:

- [FortiFlex API on page 80](#)
- [FortiFlexVM Terraform provider on page 82](#)
- [Ansible Collection on page 82](#)

FortiFlex API

Instead of making changes to your FortiFlex objects in the FortiCloud portal, you can automate tasks, such as creating VMs and entitlements, with an API when integrating with cloud orchestration platforms.



FortiFlex API information can also be found on the [Fortinet Developer Network](#) along with [sample Python script](#).

When implementing the FortiFlex API, you can follow this general process:

1. Create an API user.
2. Acquire the API token.
3. Run API calls against the FortiFlex portal to view, create, or modify objects.



Before you begin, ensure that you have a FortiCloud account and have FortiFlex activated.

To create an API user:

1. Go to <https://support.fortinet.com>.
2. Go to *Services > IAM*.
3. Create an active permission profile that includes the FortiFlex portal. See [Creating a permission profile](#) in the Identity & Access Management (IAM) guide.



Actions that involve changing or creating data, such as creating a new configuration or updating a VM, will require read and write permissions or above.

-
4. Create an API user with the permission profile from the previous step applied. See [Adding an API user](#) in the Identity & Access Management (IAM) guide.

- Click *Download Credentials* and set a password. A CSV file with the API user's credentials is downloaded that can only be opened with the password. See [Adding an API user](#) in the Identity & Access Management (IAM) guide.



Downloading API user credentials will reset the user's security credentials each time you perform this action. Any previous password will become invalid.

To acquire the API token:

- Open the Postman app.



The Postman API Toolkit can be found at <https://www.postman.com>. FortiFlex Postman collections can also be found on [GitHub](#).

- Click *Create a request*.
- Enter the following information:

Method	POST
URL	https://customerapiauth.fortinet.com/api/v1/oauth/token/

- Click *Body*.
- Select *raw* and *JSON*.
- Enter the following content:

```
{
  "username": "<username of your API user>",
  "password": "<password of your API user>",
  "client_id": "flexvm",
  "grant_type": "password"
}
```

- Click *Send*. If authentication is successful, you should receive a 200 response code with the following information:
 - `access_token`: The API token that will be used to run API calls against the FortiFlex portal.
 - `expires_in`: The token expiration time in seconds. The default value is 1440 seconds.
- Copy the `access_token` value.

To run API calls:

- Click on the **+** to open a new tab in the Postman app.
- Click *Authorization*.
- Set *Type* to *Bearer Token*.
- Paste the `access_token` value in the *Token* field.



The URL for the API calls is <https://support.fortinet.com>.

FortiFlexVM Terraform provider

The FortiFlexVM Terraform provider is used to interact with the resources supported by FortiFlexVM. The provider must be configured with the proper credentials before it can be used. See the [FortiFlexVM Documentation](#) on the Terraform Registry for information on available resources, data sources, and so on.



The FortiFlexVM provider requires:

- A FortiCloud account.
 - FortiFlex registered.
 - An API token. See [FortiFlex API on page 80](#).
-

Ansible Collection

The FortiFlex Ansible Collection can be used to run playbooks to interact with FortiFlex. The FortiFlex Ansible Collection can be found on [GitHub](#) and [Ansible Galaxy](#). See the [Ansible Galaxy FortiFlexVM Collection Documentation](#) for more information on using Ansible Galaxy, running a playbook, available modules, and so on.



You can get support from the Fortinet Inc. [Technical Assistance Center](#) or from the community engineering team by filing an issue in the [GitHub issues page](#). For support with common Ansible issues, you can get support from the [Ansible community](#).

Tools

The topics in this section provide information about the points calculator tool:

- [Points calculator on page 83](#)
- [Daily points on page 85](#)



The points calculator in the FortiFlex portal should be used to calculate points consumption for existing FortiFlex programs only. It should not be used for new deals.

Points calculator

Use the points calculator to calculate how many points will be consumed before you create a new configuration.



The points calculator can be found in the *Tools > Points Calculator* page, on the Fortinet Developer Network (<https://fdn.fortinet.net/index.php?/tools/fortiflex/>) or accessed through an API endpoint. Accessing the calculator through an API endpoint provides the current price, latest price, and effective date for the latest price.

To calculate points for a configuration:

1. Go to *Tools > Points Calculator*.
2. From the list select one of the following options.
 - *FortiGate Virtual Machine - Service Bundle*
 - *FortiGate Virtual Machine - A La Carte Services*
 - *FortiWeb Virtual Machine - Service Bundle*
 - *FortiManager Virtual Machine*
 - *FortiClient EMS On-Prem*
 - *FortiAnalyzer Virtual Machine*
 - *FortiPortal Virtual Machine*
 - *FortiADC Virtual Machine*
 - *FortiSOAR Virtual Machine*
 - *FortiMail Virtual Machine*
 - *FortiNAC Virtual Machine*
 - *FortiGate Hardware*
 - *FortiAP*
 - *FortiSwitch*
 - *FortiWeb Cloud - Private*

- FortiClient EMS Cloud
- FortiSASE
- FortiEDR-MSSP
- FortiNDR Cloud
- FortiRecon
- FortiSIEM Cloud
- FortiDLP
- FortiManager Cloud
- FortiDeceptor Cloud

3. Configure the instance based on the service you selected. The configuration settings will vary depending on the service. For more information, see [Service offerings on page 16](#)

The screenshot shows the 'Points Calculator' interface for the 'FortiGate Virtual Machine - Service Bundle'. The 'Product Type' dropdown is set to 'FortiGate Virtual Machine - Service Bundle'. The 'Number of VMs' input is set to 1. The 'Number of CPUs' dropdown is set to 1. The 'Service Package' dropdown is set to 'Standard'. The 'Virtual Domains' input is set to 0. The 'Daily Points' result is 0.00. A 'Calculate' button is visible at the bottom right.

4. From the number of *Number of VMs* dropdown, select the number of VMs.
5. Click *Calculate*. The number of points is displayed.

The screenshot shows the 'Points Calculator' interface for the 'FortiAnalyzer Virtual Machine'. The 'Product Type' dropdown is set to 'FortiAnalyzer Virtual Machine'. The 'Number of VMs' input is set to 1. The 'Daily Storage (GB)' input is set to 5. The 'Number of ADOMs' input is set to 1. The 'Support Services' dropdown is set to 'FortiCare Premium'. The 'Daily Points' result is 4.27. A 'Calculate' button is visible at the bottom right.



The *Daily Points* may display both current and latest pricing. See [Daily points on page 85](#) for more information.

Daily points

When the daily rates of a product are updated, the *Daily Points* will display both the *Current Pricing* and *Latest Pricing* for the points calculator:

- *Current Pricing*: Displays the daily point cost for the total entitlements configured. This is calculated using the fixed ratings from when the program was registered. This fixed rating is valid for up to one year and is not subject to fluctuations in program ratings.
- *Latest Pricing (as of YYYY-MM-DD)*: Displays the cost based on the latest pricing as of the date that the points calculator tool is used. This rate is the new rate that will be applied to the configured entitlements after the next anniversary date, beginning on the date displayed. This rate is an estimate based on current rates and is subject to fluctuations.

The screenshot shows the 'Points Calculator' interface. It features a blue header bar with the title 'Points Calculator' and a help icon. The main area is divided into several sections for configuration:

- Product Type***: A dropdown menu showing 'FortiGate Virtual Machine - Service Bundle'.
- Number of Flex Entitlements***: A text input field containing the value '1'.
- Number of CPUs ***: A text input field containing the value '1'.
- Service Package ***: A dropdown menu showing 'UTP'.
- Virtual Domains**: A text input field containing the value '0'.
- FortiGuard Services**: A list of checkboxes including 'Advanced Malware Protection', 'AI-Based In-line Sandbox', 'FortiGuard OT Security Service' (checked), 'FortiGuard DLP', 'FortiGuard Attack Surface Security Service', and 'FortiConverter Service'.
- Cloud Services**: A list of checkboxes including 'FortiGate Cloud Management', 'SD-WAN Underlay' (checked), 'SOCaaS', 'FortiAnalyzer Cloud', 'Cloud-based Overlay-as-a-Service', and 'SD-WAN Connector for FortiSASE'.
- Support Services**: A list of checkboxes including 'FC Elite Upgrade'.

At the bottom, there are two pricing options:

- [Daily Points - Current Pricing](#): 4.68
- [Daily Points - Latest Pricing \(as of 2024-03-20\)](#): 3.60

A blue 'Calculate' button is located at the bottom right of the form.



www.fortinet.com

Copyright© 2025 Fortinet, Inc. All rights reserved. Fortinet®, FortiGate®, FortiCare® and FortiGuard®, and certain other marks are registered trademarks of Fortinet, Inc., and other Fortinet names herein may also be registered and/or common law trademarks of Fortinet. All other product or company names may be trademarks of their respective owners. Performance and other metrics contained herein were attained in internal lab tests under ideal conditions, and actual performance and other results may vary. Network variables, different network environments and other conditions may affect performance results. Nothing herein represents any binding commitment by Fortinet, and Fortinet disclaims all warranties, whether express or implied, except to the extent Fortinet enters a binding written contract, signed by Fortinet's Chief Legal Officer, with a purchaser that expressly warrants that the identified product will perform according to certain expressly-identified performance metrics and, in such event, only the specific performance metrics expressly identified in such binding written contract shall be binding on Fortinet. For absolute clarity, any such warranty will be limited to performance in the same ideal conditions as in Fortinet's internal lab tests. Fortinet disclaims in full any covenants, representations, and guarantees pursuant hereto, whether express or implied. Fortinet reserves the right to change, modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.