


Deployment Guide

FortiSOAR Cloud 7.6.4



FORTINET DOCUMENT LIBRARY

<https://docs.fortinet.com>

FORTINET VIDEO LIBRARY

<https://video.fortinet.com>

FORTINET BLOG

<https://blog.fortinet.com>

CUSTOMER SERVICE & SUPPORT

<https://support.fortinet.com>

FORTINET TRAINING & CERTIFICATION PROGRAM

<https://www.fortinet.com/training-certification>

FORTINET TRAINING INSTITUTE

<https://training.fortinet.com>

FORTIGUARD LABS

<https://www.fortiguard.com>

END USER LICENSE AGREEMENT

<https://www.fortinet.com/doc/legal/EULA.pdf>

FEEDBACK

Email: techdoc@fortinet.com



November, 2025

FortiSOAR Cloud 7.6.4 Deployment Guide

00-400-000000-20210416

TABLE OF CONTENTS

Change Log	5
Introduction	6
FortiSOAR Cloud Virtual Machine Specifications	6
Licensing	6
FortiSOAR Cloud license contract registration	7
Deploying FortiSOAR Cloud	9
Troubleshooting	13
Uniqueness error when adding a tenant in an MSSP setup using the Secure Message Exchange	13
Beginning with FortiSOAR Cloud	14
Accessing FortiSOAR Cloud	14
Accessing FortiSOAR Cloud console	18
Accessing FortiSOAR Cloud UI	19
Switching between Accounts	19
Secure Message Exchange	21
Cloud App Menu	21
Settings	22
User Preferences	22
List of logs that can be used for debugging FortiSOAR Cloud	24
Adding an organization	25
Adding a secondary account	26
Adding a secondary account using IAM	26
Adding a secondary account using FortiCare	32
Setting up External IdP roles	34
Identifying the public IP address	36
High Availability Capability for FortiSOAR Cloud	37
Creating a cluster on the FortiSOAR Cloud portal	37
Managing a cluster on the FortiSOAR Cloud portal	38
Backing up and Restoring FortiSOAR Cloud	41
Prerequisites	41
Backup Process	41
Data that is backed up during the backup process	42
Prerequisites for running the backup process	42
Performing a backup	42
Restoring data	43
Troubleshooting	44
Migration of FortiSOAR Cloud MSSP setup fails with the Secure Message Exchange Invalid credentials or certificate error	44
Upgrading FortiSOAR Cloud	45
Upgrading your FortiSOAR Cloud instance	45
Upgrading your FortiSOAR Cloud instance using the FortiSOAR Cloud portal	46
Upgrading your FortiSOAR Cloud instance by opening a Support ticket	47

Expanding resources for your FortiSOAR Cloud instance	47
Appendix A - Supported Regions	48

Change Log

Date	Change Description
2025-11-19	Initial release of 7.6.4

Introduction

FortiSOAR Cloud is a cloud-hosted Security Orchestration & Automated Response (SOAR) platform, available via subscription through an a la carte SKU. FortiSOAR Cloud simplifies deployment, management, and scaling by eliminating the need for users to provision a virtual machine (VM) in their environment.

FortiCloud automatically sets up a cloud-based FortiSOAR instance with an integrated secure message exchange under your user account. Starting from release 7.6.0, FortiSOAR Cloud supports provisioning multiple FortiSOAR instances per account, enabling active-active clustering for horizontal scaling. For more details, see the [High Availability Capability for FortiSOAR Cloud](#) chapter.

Starting with release 7.6.1, Fortinet offers a managed upgrade service for FortiSOAR Cloud customers, simplifying the upgrade process. For more information, see the [Upgrading FortiSOAR Cloud](#) chapter.

This section includes the following topics:

- [Specifications](#)
- [Licensing](#)

FortiSOAR Cloud Virtual Machine Specifications

The FortiSOAR Cloud VM has the following default specifications:

- 12 available vCPUs
- 48 GB available RAM
- 1 TB available disk space: Recommended to have high-performance storage, preferably SSDs.
- 1 vNIC

High-volume systems (e.g., those with large alert ingestion or playbook execution) may require additional resources. Scale your FortiSOAR Cloud deployment by purchasing additional CPU, RAM, and Storage SKU, or by deploying a multi-node cluster. Contact your sales team for scalability and sizing details. For more information on expanding resources for your FortiSOAR Cloud instance, see the [Upgrading FortiSOAR Cloud](#) chapter.

A FortiCloud account is required to provision FortiSOAR Cloud. If you do not have one, create a FortiCloud account [[here](#)]. Access to FortiSOAR Cloud requires a primary FortiCloud account, which can invite secondary users to access FortiSOAR Cloud.

Licensing

You can purchase various FortiSOAR Cloud subscription licenses, including:

- FortiSOAR Cloud Enterprise License
- FortiSOAR Cloud MultiTenant Edition - Manager

- FortiSOAR Cloud Dedicated Tenant
- FortiSOAR Cloud Regional SOC

Each FortiSOAR Cloud instance license grants one VM instance for the duration of the license. Multiple instance licenses must be purchased to create a multi-node cluster, where clustering is supported by the license type.

Additional subscription feature licenses are available, including:

- FortiSOAR Cloud Threat Intel Management
This licensing option for the Threat Intelligence Management (TIM) Service includes FortiGuard Premium Threat Feeds, granting full access to TIM features, including unrestricted consumption of FortiGuard feeds. For details on unrestricted FortiGuard threat feeds, premium TIM features, and TIM SKUs, see the [Licensing](#) chapter in the FortiSOAR "Deployment Guide." For more information on TIM, see the [Threat Intel Management Solution Pack](#) documentation.
- FortiSOAR Cloud User Seat License
- FortiSOAR Cloud per-VM storage, CPU, and RAM Add-On, see the [Upgrading FortiSOAR Cloud](#) chapter for details

Contact your sales team to discuss licensing in detail.

A license expiration warning is displayed 30 days in FortiSOAR before the expiration date. Customers have a 3-day grace period to renew their contract and maintain access to the VM. After the grace period, the cloud portal will be inaccessible:

The screenshot displays the FortiSOAR Cloud management interface. The top navigation bar includes 'FortiSOAR Cloud', 'Service', and 'Support'. The user is logged in as 'admin.fsr@mailinator.com'.

The main content area is divided into three sections:

- Account Information:** Shows details for Account ID 1691118, Owner FSR ADMIN, Account Email admin.fsr@mailinator.com, Company FortiSOAR, and Service Regions Canada (Vancouver)-3.
- Assets:** Lists three assets with their IDs and status:

Asset ID	Status
FSRCLDTM23090082	Active (Green checkmark)
FSRCLDTM24090055	Expired (Red X)
FSRCLDTM24090056	Active (Green checkmark)
- Instances / Clusters:** Shows a table of clusters:

Cluster	Region	Status	Health	Actions
Master Cluster	CA-WEST-3	Active (Green checkmark)	Available	Manage Cluster, Login
Master Cluster	CA-WEST-3	Active (Green checkmark)		Manage Cluster
Test	CA-WEST-3	Active (Green checkmark)		Manage Cluster

FortiSOAR Cloud license contract registration

1. Ensure you have a FortiCare account.
2. Contact FortiSOAR Support for the FortiSOAR Cloud product SKU.
Note: By default, the FortiSOAR Cloud product SKUs comes with two users included. Additional users can be added by purchasing the 'Additional Users Entitlement' SKU.
3. Once you complete purchasing the FortiSOAR Cloud product SKU and/or the 'Additional Users' SKU, you will receive a service contract registration code at your registered email address.
4. Login to your FortiCare account and click **Asset > Register/Activate** to register your FortiSOAR Cloud product. Register your FortiSOAR Cloud product by following the instructions provided in the FortiCare

registration wizard.

Copy and paste the service contract registration code from the email to register FortiSOAR Cloud. After verification, click **Complete** to finalize the registration.

Deploying FortiSOAR Cloud

This section provides instructions on deploying FortiSOAR Cloud.

To deploy FortiSOAR Cloud:

1. Ensure that you have a product entitlement for FortiSOAR Cloud and note your account ID number in the FortiCloud portal:

The screenshot shows the FortiCloud portal interface. On the left is a navigation menu with 'ASSET MANAGEMENT' and 'Products'. The main area displays a table of products under the heading 'View Products: 18 Units'. The table has columns for SERIAL NUMBER, PRODUCT MODEL, DESCRIPTION, and dates. One row is highlighted: 'FSRCLDTM24090068' with 'FortiSOAR Cloud' as the product model and 'FortiSOAR Cloud For HA' as the description. In the top right corner, a user profile dropdown menu is open, showing the account ID '1691118/FortiSOAR' highlighted with a red box. Other options in the menu include 'My Account', 'Security Credentials', 'Switch Accounts', and 'Logout'.




Wait for 30 minutes after creating a FortiCloud account before proceeding to the next step.


2. Access your FortiSOAR Cloud instance by clicking **Services** on the FortiCloud portal, and then selecting **FortiSOAR Cloud** from the CCloud Management section:

The screenshot shows the FortiCloud portal with the 'Services' section selected. The interface is divided into three main columns: 'ASSETS & ACCOUNTS', 'CLOUD MANAGEMENT', and 'CLOUD SERVICES'. In the 'CLOUD MANAGEMENT' column, 'FortiSOAR Cloud' is highlighted with a red box. Other services listed include FortiClient EMS Cloud, FortiAnalyzer Cloud, FortiLAN Cloud, FortiSIEM Cloud, FortiGate Cloud, FortiManager Cloud, and FortiExtender Cloud. The 'CLOUD SERVICES' column lists a wide variety of other services like FortiSASE, FortiMonitor, FortiRecon, etc. The top navigation bar includes 'FortiCloud', 'Services', 'Support', and a user profile dropdown.


- Once you log onto FortiSOAR Cloud, from the left menu select the 'Master' FortiSOAR account. This displays all the information associated with this account including the dedicated instance's Account ID:




- In the Asset section, click **Provision** next to the license serial number of the FortiSOAR instance you wish to provision. This opens the Provision Service page, where you can choose the **Region** for provisioning the instance:




- Once you select the region, click **Submit**. Clicking **Submit** opens the following confirmation dialog:



6. Clicking **Confirm** opens an **Acceptance of Terms and Policies** dialog:



Select the Terms and Policies and click **Accept** to initiate the provisioning of the FortiSOAR instance. The provisioning process takes a few minutes:




During provisioning, initial configuration steps for FortiSOAR are performed. These steps include running the automated, non-interactive FortiSOAR configuration wizard, enabling the embedded Secure Message Exchange, triggering the heartbeat between FortiCloud and FortiSOAR, and installing the selected license.



FortiSOAR VM provisioning is considered successful only after FortiCloud receives the first heartbeat from FortiSOAR.

If there are any provisioning failures, such as failures during the initial configuration phase using the automated non-interactive FortiSOAR configuration wizard, including failures while configuring the embedded Secure Message Exchange, then a failure screen detailing the status of each configuration step is displayed, making it simpler to identify the issue. Before using FortiSOAR Cloud, you must use WebSSH to fix any issues with the failed steps as their functioning might be hampered. However, if you choose to access FortiSOAR Cloud without rectifying the failed steps, which can cause FortiSOAR functionality to deteriorate, a **Proceed Anyway** button is provided that lets you to use the product while acknowledging the configuration failure:



If your instance is not accessible even after clicking **Proceed Anyway**, you can try the following steps to fix the issues:

- Restart all the services using the `csadm services --restart` command.
- Manually install ansible in the case of an ansible installation error using the following command:
`sudo -u nginx /opt/cyops-workflow/.env/bin/pip install ansible==7.4.0 --extra-index-url https://repo.fortisoar.fortinet.com/prod/connectors/deps/simple/`
- If the failure screen keeps getting displayed on the FortiSOAR Cloud UI, even after you have attempted to resolve all the backend issues, then you can update the `fsr-boot.json` to update its state from 'failed' to 'config_vm_failure_acknowledged'.

Contact support if failures persist even after troubleshooting.

Once provisioned successfully access the FortiSOAR web GUI by clicking **Login** or click **WebSSH** to access the FortiSOAR console to begin using FortiSOAR Cloud. For more information, see the [Beginning with FortiSOAR](#)

Cloud chapter.

Important notes to be considered before starting to use FortiSOAR Cloud instance:

- After provisioning the FortiSOAR Cloud instance, it is highly recommended that you log in to the WebSSH interface and immediately change the default 'csadmin' user's password. This step enhances the security of your FortiSOAR Cloud instances.
- Only the primary account holder can create secondary account holders in FortiCloud. Secondary account holders can log in as restricted users to the same instance. The primary account holder can modify the admin profile for the secondary user. For more information, see the [Adding a secondary account](#) chapter.
- It is highly recommended to set up a backup user for the FortiSOAR appliance. This allows access to the CLI in case the 'csadmin' CLI password is forgotten or the csadmin user gets locked. For the steps to create a backup user, see the [Creating a backup user for the FortiSOAR appliance to allow access to the CLI](#) topic in the *Deploying FortiSOAR* chapter of the "Deployment Guide."
- To restrict access to your FortiSOAR instance, contact the FortiCloud team to add IP addresses to the allowlist. Once added, only those IP addresses can access your FortiSOAR instance.

Troubleshooting

Uniqueness error when adding a tenant in an MSSP setup using the Secure Message Exchange

The embedded Secure Message Exchange (SME) that is enabled by default in the case of FortiSOAR Cloud throws the uniqueness error only when the tenant and master nodes are located in the same Cloud region.

Resolution


To resolve this issue, make sure to update the name of the SME on either the master node or the tenant node before configuring your MSSP setup.

Beginning with FortiSOAR Cloud


Accessing FortiSOAR Cloud

You can access FortiSOAR Cloud in the following ways:

- Using fortisoar.fortinet.com - This displays the FortiSOAR Cloud portal's landing page:




Clicking **Log in** displays the Organization Unit (OU) or Accounts page, which lists the master account and all the sub-user accounts:



Select the account whose details you want to view.

- Using support.fortinet.com - This directly displays the Organization Unit (OU) or Accounts page if the FortiSOAR Cloud instance is provisioned with a valid license.

Selecting an account Organization Unit (OU) or Accounts page displays a page containing the details of that account, as well as any assets, instances, and clusters associated with it:




The **Master** tag is used to indicate the master account while the rest are sub-user accounts.

NOTE: Provisioning can only be done by the 'Master' account.

The account page also displays the following details:

- **Account Information:** Displays general information about the account including its ID, owner, email address, company, and service region.
- **Assets:** This section displays a list of assets (active licensed instances) associated with account, categorized as follows based on the icons/buttons next to each asset:

- **Green Check** icon: Successfully provisioned instance.
- **Blue Provision** button: Instance yet to be provisioned.
- **Red Provision** button: Provisioning failure for the instance.
NOTE: If provisioning fails for an instance, you can view the details of the failure by clicking on the **Red Provision** button.
- **Expired** text in red: License for the instance has expired:



- **Instances/ Clusters:** This section includes the following tabs:
 - **Standalone Instances:** Displays a list of provisioned standalone instances that are not part of any cluster. Each row provides brief details of the instance including its version, expiration date, region and status. You can also use the following buttons:
 - **Login:** To access the FortiSOAR UI. For more information, see the [Accessing FortiSOAR Cloud UI](#) topic.
 - **WebSSH:** To access the FortiSOAR Cloud console. For more information, see the [Accessing FortiSOAR Cloud console](#) topic.
 - **Manage Instance:** To view the Instance page that contains details about that instance and is used to manage the instance. For more information, see the [Instance page details](#) topic.
 - **Clusters:** Displays a list of clusters. Each row provides brief details of the cluster including its name, region, status, and health. Click the arrow to expand the cluster row and view information about instances in the cluster. You can also use the following buttons:
 - **Login:** To access the FortiSOAR UI. For more information, see the [Accessing FortiSOAR Cloud UI](#) topic.
 - **Manage Cluster:** To view the Cluster Info page that contains details about that cluster and is used to manage the cluster. For information about cluster instances, see the [High Availability capability for FortiSOAR Cloud](#) chapter.

Instance page details

The Manage Instance page provides details such as the instance ID, license information, disk usage etc.

The screenshot displays the FortiSOAR Cloud instance management interface. The top navigation bar includes 'FortiSOAR Cloud', 'Service', and 'Support'. The user is logged in as 'admin.fsr@mailinator.com'.

The main content area is divided into several sections:

- Instance Information:** Contains two tabs: 'General' and 'Cluster Node Info'. The 'General' tab shows:
 - Instance ID: ad3a5012-9cbc-4fe3-ad14-0f7de675c18a
 - Expiration Date: 2025-11-14
 - License SN: FSRLDTM24090338
 - Service Version: v7.6.1-build5275
 - Region: CA-WEST-3
 - Status: Active
 A 'Reboot' button is located at the bottom of this section.
- License Details:** A table showing license information:

Support Type Desc	Type	Level	Start Date	End Date	Status
FortiSOAR Multi Tenant - Regional S...	143	6	14 Nov 2024	14 Nov 2025	Active
FortiSOAR User Login	144	6	14 Nov 2024	14 Nov 2025	Active
- Disk Usage:** A donut chart showing 0.84% usage. Below the chart, it states: 'Disk: 1000.00 GB Used: 8.40 GB'.
- Resource Usage:** Two progress bars:
 - vCPU (8): 1.5%
 - RAM (32 GB): 32.2%
- Upgrade:** A section with the text: 'You can raise an upgrade request for your FortiSOAR instance by clicking on "Initiate Upgrade Request" button'. A blue 'Initiate Upgrade Request' button is present.

At the bottom of the page, there are links for 'Terms of Service', 'Privacy Policy', 'Release Notes', and 'Feedback'. The footer includes 'v24.4 b5029 Copyright © 2024 Fortinet, Inc. All rights reserved.'

It includes the following sections:

- **Instance Information:** This section has two tabs, General and Cluster Node Info. You can reboot the instance by clicking the **Reboot** button.
 - **General:** Displays details such as the instance ID, its expiration date, FortiSOAR release on which the instance is provisioned, such as release 7.5.0-4015, its status, etc.
 - **Cluster Node Info:** If the instance is part of a cluster, then this tab shows information about the node's role, health, and status, etc.
- **License Details:** Displays details such as the type of license deployed on the instance, the start and end date for the license, etc.
- **Disk Usage:** Displays disk usage details in percentage and numbers.
- **Resource Usage:** Displays the vCPU and RAM usage.


NOTE: If you need to expand the resources for your FortiSOAR Cloud instance, follow the Expanding resources for your FortiSOAR Cloud instance process mentioned in the [Upgrading FortiSOAR Cloud](#) chapter.
- **Upgrade:** Fortinet offers a managed upgrade service for FortiSOAR Cloud customers, simplifying the upgrade process. To initiate an upgrade, click the **Initiate Upgrade Request** button. For more information on the upgrade process, see the [Upgrading FortiSOAR Cloud](#) chapter.

Accessing FortiSOAR Cloud console

To access the FortiSOAR Cloud console, click **WebSSH** on the FortiCloud portal. If you are logging into the console for the first time, then you must enter the default SSH credentials, which are `csadmin/<your_account_id>`. You will be asked to change the default SSH passwords after successfully logging into the console:

```
You are required to change your password immediately (administrator enforced)
-----
Built on: 2023-06-24
Rocky Linux Version: 8.8
FortiSOAR Version: 7.4.1-3167
-----
WARNING: Your password has expired.
You must change your password now and login again!
Changing password for user csadmin.
Current password:
```

Once you update the default password, you will be logged out and again asked to log in using the updated credentials. Once you log in, you will be presented with the EULA acceptance pages (2 pages):



Click **Accept** to accept the EULA. Once the EULA is accepted, you can start to use the FortiSOAR Cloud console. You can use the FortiSOAR Cloud console and perform various administrative tasks using the 'csadm' commands

on the console:

```
-----
Built on: 2023-06-24
Rocky Linux Version: 8.8
FortiSOAR Version: 7.4.1-3167
-----
Last login: Thu Aug 24 08:46:57 2023 from 10.96.131.138

[csadmin@1693448 ~]$ sudo su
[root@1693448 csadmin]# csadm
usage: csadm [<subcommand> <options>]      Run subcommand
        [<subcommand> --help]             Show detailed help of subcommand
        [--help]                           Show this message

csadm subcommands are:
  certs          - Generate and deploy certificates
  db             - Manage database
  hostname       - Change hostname
  license        - Manage license
  user           - Manage users
  log            - Manage log
  mq             - Manage message queue
  secure-message-exchange - Manage Default (Embedded) Secure Message Exchange
  source-control - Source control allows import / export FSR configurations, for CICD
  network        - Manage network
  services       - Manage services
  ha             - Manage HA cluster
  system         - Manage system settings
  package        - Manage package
[root@1693448 csadmin]#
```

Accessing FortiSOAR Cloud UI

To access the FortiSOAR UI, click **Login** on the FortiCloud portal. On the FortiSOAR UI, you will be asked to accept the EULA if it is not already accepted. Once you accept the EULA, you will be logged into the FortiSOAR UI. The role that you have been assigned, i.e., a 'Full Access' user or a 'Limited Access' user, determines the actions you can perform in FortiSOAR. For information on FortiSOAR features and how to use and configure them, see the [FortiSOAR Documentation Library](#).


By default, the SOAR Framework Solution Pack is installed on FortiSOAR Cloud. The SOAR Framework Solution Pack (SP) is the **Foundational** Solution Pack that creates the framework, including modules, dashboards, roles, widgets, etc., required for effective day-to-day operations of any SOC. Also, the Incident Response modules, i.e., Alerts, Incidents, Indicators, and War Rooms, are not part of the FortiSOAR Cloud platform, making it essential to optimally use and experience FortiSOAR Cloud's incident response. For detailed information about the SOAR Framework SP, see the [SOAR Framework SP](#) documentation.

Switching between Accounts


You can switch between your available accounts using the **Profile** menu. If you are signed in with your email credentials, you can switch to any linked user accounts. Note that available options may vary depending on your account permissions and linked accounts.

To switch to a new account:

1. Click your **Profile** icon in the top-right corner.
2. Select **Switch Accounts**:




3. In the **Make a Selection to Proceed** dialog, select the user account you want to switch:



To switch to a different Organizational Unit (OU) account:

Note: This process applies to **IAM and IdP users** only.

1. Open the **OU Account Selection** drop-down menu. Accounts within your organization are displayed:



2. Select an account within your available scope (OU) by hovering over the appropriate member account and clicking **Select**.

Secure Message Exchange

The FortiSOAR Cloud instance contains an embedded FortiSOAR Secure Message Exchange (SME). A secure message exchange establishes a secure channel that is used to relay information to external agents or dedicated tenant nodes. The address of the embedded SME is set as the Cloud portal address, and Server Name Indication to the instance URL. The embedded SME runs on port 5671.




If a FortiCloud account is migrated, you must update the Server Name Indication to the URL of the new instance.

In case of a cluster, the Server Name Indication of the SME must be updated to the URL of the cluster. This ensures that requests are load balanced between instances.

Cloud App Menu

FortiSOAR displays an **App Menu** for users logging in through the Cloud portal. The App Menu appears in the FortiSOAR top bar and provides access to other cloud applications, such as FortiEDR and FortiAnalyzer Cloud. It also includes a **Search** bar for searching across assets, accounts, apps, and services:



When you click on another cloud app, such as FortiAnalyzer Cloud, you will be redirected to that app's cloud portal and logged out of both FortiSOAR and the FortiSOAR Cloud Portal. Clicking the **Log Out** button will also log you out of both FortiSOAR and the FortiSOAR Cloud Portal.

Settings

The 'Settings' icon in the top bar allows administrators to customize FortiSOAR Cloud and configure default options used throughout the system. For more information, see the "Administration Guide" that is part of the [FortiSOAR Documentation](#).

FortiSOAR supports internationalization via a system widget named "Language Pack" that includes the supported languages. This widget is automatically installed during the installation or upgrade of FortiSOAR Cloud to release 7.5.0 or later.



The "Language Pack" widget is a system widget that cannot be uninstalled, and you should not modify it. Making changes to it can result in translation issues, causing the FortiSOAR Cloud UI to appear in English. English serves as the fallback language for FortiSOAR Cloud. Any content that is not translated will be shown in English.


Administrators must be assigned the 'Read' or 'Usage' permission on 'Widgets' (in addition to other necessary permissions) to modify the global language settings. Without this permission, the FortiSOAR UI remains in English, regardless of the language you set. Administrators can set the language for FortiSOAR from the supported options:

- English (Default)
- Japanese (Preview)
- Korean (Preview)
- Simplified Chinese (Preview)
- French (Preview) [added in FortiSOAR release 7.6.4]
- Traditional Chinese (Preview) [added in FortiSOAR release 7.6.4]

This language setting will apply to all users; however, users can set their language preference in their user profile, and the user's preference will take precedence over the administrator's setting.

User Preferences

The 'user profile' icon in the top bar allows users without access to the 'Security' module to edit their profile. You can customize your profile to set the email notification options, theme, and language for your FortiSOAR instance:



To edit your user preferences, click the **User Profile** icon to display the User Profile dialog. On the User Profile dialog, you can set the following preferences:

- In the Notifications section, set your notifications preference:
 - Select **Enable System notifications on email** to receive system notifications on your email account.
 - Select **Enable email notifications for @mentions in comments** to receive notifications for @ mentions in comments.
- In the Themes Settings section, select the FortiSOAR theme you want to use; you can choose between **Dark**, **Light**, and **Space**, with **Space** being the default. Click **Preview Theme** to see the UI in the selected theme. To go back to the original theme, after previewing the theme, click **Revert Theme**.
- In the Language Settings section, set your language preference from the supported options: English, Japanese (Preview), Korean (Preview), Simplified Chinese (Preview), French (Preview) [added in FortiSOAR release 7.6.4], and Traditional Chinese (Preview) [added in FortiSOAR release 7.6.4]. Starting with release 7.5.0, FortiSOAR supports internationalization via a system widget named "Language Pack" that includes the supported languages.

NOTE: To customize the language for your FortiSOAR instance, you must be assigned the 'Read' or 'Usage' permission on 'Widgets'. Without this permission, the UI of your FortiSOAR instance will remain in English, regardless of the language you set in your profile.

Your preferred language will take precedence over the administrator's setting. For example, if the administrator has set the language to 'Korean', but you prefer 'Japanese', you can select Japanese in your profile, and the UI of your instance will be displayed in Japanese.

To set your language preference, from the **Select a Language** drop-down list select your preferred language.

Once you have completed updating your profile, click **Save** on the User Profile dialog.

List of logs that can be used for debugging FortiSOAR Cloud



If you face any issues with your FortiSOAR Cloud instance, contact Fortinet Support for assistance.


Additionally, administrators can use various logs that FortiSOAR generates to troubleshoot FortiSOAR Cloud issues:

Log Name	Purpose
<code>/var/log/cyops/install/config-vm-<time-stamp-here>.log</code>	Used for troubleshooting issues that occur while configuring the VM.
<code>/var/log/cyops/fcloud/</code>	Used for troubleshooting issues related to other cloud-related apps.
<code>/var/log/cyops/csadm/secure-message-exchange.log</code>	Used for troubleshooting issues related to the secure message exchange.

Adding an organization

You can create an organization for FortiSOAR Cloud. An organization is a centralized account management service that consolidates multiple FortiSOAR Cloud accounts into Organization/Organizational Units (OUs). The service offers a unified management interface across FortiCloud accounts to manage assets and cloud services, inviting accounts, hierarchical account grouping (OUs), and access roles for user permissions. For more information, see the [FortiCloud Account Services Organization Portal](#) documentation.

Create your organization, for example, 'Fortinet FortiSOAR', using the steps mentioned in the [FortiCloud Account Services Organization Portal](#) documentation. The account used to set up the organization serves as the 'root' account. Authorized users can add OUs and invite members to join the organization. OUs act as folders to organize accounts and establish the organizational structure. You can create up to three levels of OUs:



After creating the Organization and OUs, you can invite Member Accounts to join the OUs using invitation tokens as described in the [FortiCloud Account Services Organization Portal](#) documentation. Additionally, you can add an administrative IAM user for the organization to create and manage IAM users within the OUs. For more information see the [Adding a secondary account](#) chapter.

Adding a secondary account


You can create a secondary account for FortiSOAR Cloud to allow the Fortinet support team to troubleshoot FortiSOAR Cloud deployment. A secondary account can be added using Identity & Access Management (IAM), or FortiCare, or by setting up External IdP roles. IAM helps manage access to FortiSOAR Cloud portals and assets, allowing control over users, authentication credentials, and asset permissions.



Organizational Units (OUs) are only visible to IAM users, not to secondary users added using FortiCare.


Adding a secondary account using IAM

1. Login to <https://support.fortinet.com/>.
2. Navigate to **Services > IAM**.




3. Before you can create IAM users, you must create permission profiles. Permission profiles define the level of portal access and permissions a user has. Permission profiles allow you to explicitly enable or disable access to FortiSOAR Cloud portals and grant portal-specific permissions for the enabled portals. To create permission profiles, do the following:


- a. Click the **Permission Profiles** menu item on the IAM portal:



- b. Click **Add New** to display the New Portal Permission Profile page:




- i. In the Basic Info section, add the required information to create the permission profile as per your requirements. For information on creating permission profiles, see the [FortiCloud Account Services Identity & Access Management](#) documentation:




- ii. Click **Add Portal** to display the Add These Portals To My Account pop-up. Use this pop-up to assign portal permissions to the user. You can assign the following permissions: Asset


Management, FortiCare, FortiSOAR Cloud, IAM, etc and click **Add**:




- iii. In the Permissions Profile section, select the access type you want to assign to the user for the selected permission profiles, and click **Submit**:




This adds the permission profile that can be assigned to users:




4. Click the **Users** menu item on the IAM portal, and then select **Add New > IAM User**:




a. On the IAM User page, add the details of the user to create a new IAM user, and then click **Next**.




- b. On the User Permissions page, assign the IAM user the appropriate permission type, scope, profile, etc., and then click **Next**:



- 5. Click **Confirm** to complete the user creation process:




- 6. On the Successful User Registration page, click **Generate Password** to generate a reset password link for the user to login.



Regenerating the password renders the previous password invalid and expires in 5 days.


7. Navigate to <https://support.fortinet.com/>.
8. Click the **IAM Login** tab:




9. Enter your account ID, username, and new (regenerated) password, and click **Log in**.
10. Once you have successfully logged in, select **Services > FortiSOAR Cloud** to start working in FortiSOAR Cloud.

Adding a secondary account using FortiCare

1. Login to <https://support.fortinet.com/>.
2. Click the user profile in the top-left corner and click **My Account** to display the Account Profile page:



3. Click **Manage User**.
4. Click the new user icon to add a new user.



5. When creating an account for the Fortinet support team, specify an email for the secondary account and select **Full Access** or **Limit Access**.
 A user with 'Full Access' has the same access level as a primary account user. A user with 'Limited Access' can only manage the assigned product serial number and will be unable to receive renewal notices or create

additional secondary account users.

6. Login to <https://support.fortinet.com/>. In the FortiSOAR Cloud section, you will see an account listed as a secondary member.
7. Click the entry to expand the view.



A secondary account can access the portal thirty days after it expires.

To modify a secondary account:




The new user must log in to FortiSOAR Cloud for the account to be displayed in the FortiSOAR instance. When a new user logs in to their account, they are automatically assigned *Admin* roles on FortiSOAR, if they are added as 'Full Access' users in FortiCare, and the *SOC Analyst* role on FortiSOAR if they are added as 'Limit Access' users in FortiCare.

The primary user or a super user can update user accounts, to, for example, change the user permissions, phone numbers, etc. as follows:

1. Use the primary or super user credentials and login to <https://support.fortinet.com/>
2. Click **My Account > Manage Users**.
The Manage User page displays a list of users.
3. Click the user whose account you want to modify to display the User Details page.
4. On the User Details page, click **Edit**.

- 5. On the Edit User page, modify the user account as required and click **Save**. For example, change the Permissions from 'Full Access' to 'Limit Access':



Setting up External IdP roles

External IdP roles enable external users to log in to the Cloud portal using their company's credentials through a third-party ID provider. The company's ID provider verifies the identity of external IdP users. Following authentication, users can access the cloud application according to their role.

Brief process to set up External IdP roles is as follows:

1. Send an enrollment request to forticloud-enroll-extidp@fortinet.com.
2. The FortiCloud team will review and approve the request.
3. Once the enrollment request is approved, the External IdP will be configured and linked to the appropriate FortiCloud accounts by the FortiCloud FAC and Customer Ops teams.

For more information on External IdP, see the External IdP roles topic in the *Identity & Access Management (IAM)* guide of the [FortiCloud Account Services](#) documentation.

Adding a secondary account

Once the External IdP integration is complete, log into FortiCloud, and ensure that the defined External IDP role has access permissions in the FortiSOAR Cloud's Permissions Profile section of the IAM portal:

PERMISSION PROFILE Add Portal

PERMISSION DETAILS

FortiSOAR Cloud			Asset Management				IAM			
Access	Access Type	Additional Permission	Resources	Read Only	Read & Write	No Access	Resources	Read Only	Read & Write	No Access
<input checked="" type="checkbox"/>	<input checked="" type="radio"/> Admin <input type="radio"/> Read/Write <input type="radio"/> ReadOnly		Entitlement Management	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>	User / Permissions	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>
			Asset Maintenance	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>	Account	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>
			Renewal Notice	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>	Credentials	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>
			Vulnerability List	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>				
			Account Services	<input checked="" type="radio"/>	<input type="radio"/>	<input type="radio"/>				

Additionally, note that after logging into FortiCloud, you are directed to the Asset Management portal, from which you can access the FortiSOAR Cloud portal using the same External IdP user access.

Identifying the public IP address

You can use the FortiSOAR Cloud CLI to determine the public IP address for FortiSOAR Cloud.

To determine the public IP address:

1. Login to <https://support.fortinet.com/>.
2. Click **Services > FortiSOAR Cloud**.
If FortiSOAR Cloud is not visible, click on the **Show More** link to reveal all the services.
3. On the FortiSOAR Cloud portal, click **WebSSH** to access the FortiSOAR Cloud console.
4. On the SSH Login page, enter the credentials to access the FortiSOAR Cloud.
5. Run the following command to get the public IP:

```
[csadmin@<primary-user-id-here> ~] $ curl ifconfig.me
```

You can use the public IP address to set up connections with third-party services, such as LDAP or the AWS Management Portal for vCenter.


High Availability Capability for FortiSOAR Cloud

FortiSOAR Cloud supports provisioning multiple FortiSOAR instances per account, allowing the creation of an active-active cluster to enable horizontal scaling.

Creating a cluster on the FortiSOAR Cloud portal


Access your FortiSOAR Cloud account as described in the [Beginning with FortiSOAR Cloud](#) chapter.

1. Click on the account where you want to create the cluster, then select the **Clusters** tab:



NOTE: Only the 'Master' account can create a cluster, and a cluster can only be created using provisioned instances.

2. Click the **+** button to open the **Cluster Create** page.
3. Enter the following details on the **Cluster Create** page, then click **Submit** to create an cluster on FortiSOAR Cloud:
 - a. **Cluster Name:** Enter the name of the HA cluster.
 - b. **Region:** Select the FortiCloud service region where you want to create the cluster.
 - c. **Instances:** Select the instances to include in the cluster.
NOTE: The FortiSOAR version and license type of the instances must match for cluster creation.
 - d. **Notes:** (Optional) Provide the support team with additional details about the HA cluster to be created. Designating a specific instance as Active/Secondary or Active/Primary in the cluster is an example of what could be added in the Notes field.




Once instances are selected, click **Submit** to create the cluster:

After clicking **Submit**, a notification is sent to Fortinet Support to set up a cluster between the selected instances and configure a load balancer. They will create a support ticket on your behalf and contact you if needed to complete the process. After the support team completes the setup, you will receive a notification and can view your cluster in your account. For detailed information on high availability support in FortiSOAR, see the [High Availability support in FortiSOAR](#) chapter in the "FortiSOAR Administration Guide".

Managing a cluster on the FortiSOAR Cloud portal


Access your FortiSOAR Cloud account as described in the [Beginning with FortiSOAR Cloud](#) chapter. On your account page, click the Clusters tab:



The cluster created in your account will display the following details:

- **Name:** Name of the cluster
- **Region:** Region where the cluster is provisioned
- **Status:** Indicates if the cluster is successfully provisioned and ready to use. It can be in the following states:
 - **Configuring:** Initial configuration and network setup for the selected instances.
 - **Active:** Cluster is successfully formed and ready to use.
- **Health:** Indicates the health of the cluster with values like Available, Requires Attention, or Error.
- You can also perform the following actions using the following available buttons:
 - **Login:** Access the FortiSOAR UI of an instance within the cluster.
NOTE: The load balancer determines which FortiSOAR instance's UI is displayed. For more information, see the Accessing FortiSOAR Cloud UI topic in the [Beginning with FortiSOAR Cloud](#) chapter.
 - **Manage Cluster:** View the Cluster Info page, which includes details about that cluster and is used to manage the cluster. For more information, see the [Cluster Info page details](#) topic.

Click the arrow to expand the cluster row and view information about instances in the cluster:



The expanded view shows the following details of the instances within the cluster:

- **Node Details**, including the instance's ID, its expiration date, and the FortiSOAR release on which the instance is provisioned.
- **Name** of the cluster associated with the instance.
- **Status** of the node, whether Active or Inactive.
- **Role** of the node, whether Primary or Secondary.
NOTE: Initially, all nodes are set as 'Primary' on FortiCloud. Roles are updated during HA cluster creation in FortiSOAR using the 'csadm ha' CLI. For information on the csadm ha command, see the [High Availability support in FortiSOAR](#) chapter in the "FortiSOAR Administration Guide".
- You can also perform the following actions using the following available buttons:
 - **Login:** Access the FortiSOAR UI of an instance.
 - **WebSSH:** Access the FortiSOAR Cloud console of an instance.
 - **Manage Instance:** View the Instance page that includes details about that instance and is used to manage the instance.
 For more information, see the [Beginning with FortiSOAR Cloud](#) chapter.

Cluster Info page details

The Cluster Info page that displays details about a cluster including its name, region, description, and status. It also lists the instances within the cluster, along with their IDs, regions, health statuses, etc.

Account: 1691118

Cluster Info

Name	Region	Status	Notes
Master Cluster	CA-WEST-3	Active	

Cluster Instances

Id	SN	Region	Version	Health	Node Role
34895f2f-fe05-4cd3-ad0d-242ffd4b911e	FSRCLDTM23090082	CA-WEST-3	v7.6.0-build4990	Available	Primary
245a8945-5974-4050-876c-b9d61558fa1d	FSRCLDTM24090055	CA-WEST-3	v7.6.0-build4990	Available	Secondary

Modify

To make changes to the cluster, click the **Modify** button to access the Modify Cluster page:

Account: 1691118

Cluster Name*

Master Cluster

Region*

Canada (Vancouver)-3

Instances

FSRCLDTM23090082 × FSRCLDTM24090055 ×

Notes

Please provide any additional information or specific instructions that you would like to share with the support team regarding the HA cluster creation. This may include special requirements if any.

Secondary Node - FSRCLDTM23090082

Cancel Submit

On the Modify Cluster page, where you can:

- Update the cluster's name or notes.
- Add or remove instances.
 - Add an instance: When you add an instance to the cluster, a notification is sent to Fortinet Support, who will update the cluster and load balancer. They will create a support ticket on your behalf and contact you if needed to complete the process. After the support team completes adding the instance to the existing FortiSOAR cluster, you will receive a notification and can view your cluster in your account.
 - Remove an instance: When you remove an instance from the cluster, the cluster on FortiSOAR will be automatically broken.

For detailed information on high availability support in FortiSOAR, see the [High Availability support in FortiSOAR](#) chapter in the "FortiSOAR Administration Guide".

NOTE: The region of the cluster cannot be changed.

Backing up and Restoring FortiSOAR Cloud

This chapter describes the process of backing up and restoring FortiSOAR Cloud.



Before release 7.5.0, FortiSOAR Cloud did not support static IP configuration for FortiSOAR Cloud, leading to issues with disaster recovery. Therefore, with release 7.5.0, support for static IP configuration in FortiSOAR Cloud deployment has been added. For the process of [Setting a static IP](#), see the [Deploying FortiSOAR](#) chapter of the "Deployment Guide."

Prerequisites

You must have root or sudo permissions to perform backups and restores.



Ensure that you have enough disk space available to perform backup and restore tasks. It is recommended that you have available disk space of around 3X the data size; for example, if your data size is 2GB, then you should have around 6GB of available disk space to ensure that the processes do not stop or fail.

Backup Process

Use the FortiSOAR Admin CLI (`csadm`) `db` option to regularly perform backups and restores, which restores the data seamlessly to a new FortiSOAR Cloud environment.

The FortiSOAR Admin CLI performs a full database backup of your FortiSOAR Cloud server each time. There is no provision for incremental backups. Backups are performed for a particular version of FortiSOAR Cloud, and backups should be restored on the exact version of FortiSOAR Cloud.



The FortiSOAR Cloud Admin CLI backs up the latest three backups every time it creates a new backup. Any backups older than the latest three backups are deleted.

Data that is backed up during the backup process

The FortiSOAR Cloud Admin CLI backs up the following files, configurations, and data during the backup process:

- site-packages
- connectors
- application.conf
- db_config.yml
- pg_hba.conf
- Syslog forwarding configuration
- All major configuration files, such as das.ini, postgresql.conf
- PostgreSQL database backups as per requirements
- User-defined custom expressions



Backups of the configuration files are taken only in the case of localized databases.

Prerequisites for running the backup process

Verify that you have the local backup storage path or NFS.

Performing a backup

To perform a backup, run the `csadm` command on any FortiSOAR Cloud machine using any terminal. A user who has root or sudo permissions can run the `csadm` command.

1. SSH to your FortiSOAR Cloud VM and login as a *root* user.

2. To perform a backup, type the following command:

```
# csadm db --backup [<backup_dir_path>]
```

[<backup_dir_path>] is the directory where backup files will be created. If you do not specify any path, then by default, the backup file is stored in the current working directory.

Optionally, you can specify the `--exclude-workflow` option to exclude all the "Executed Playbook Logs" and the `--exclude-audit` option to exclude all the "Executed Audit Logs" from the backup. Executed playbook and audit logs are primarily meant for debugging, so they are not a very critical component to be backed up. However, they constitute a major part of the database size, so excluding them from the backup reduces the time and space needed for the backup. For example, to exclude all the "Executed Playbook Logs" from the backup, type the command as follows:

```
# csadm db --backup [<backup_dir_path>] --exclude-workflow
```

Important: FortiSOAR Cloud backs up the latest three backup files every time it creates a new backup. Any backups older than the latest three backups are deleted.

3. (Optional) If you only want to back up your configuration files only, then type the following command:

```
# csadm db --backup-config [<backup_dir_path>]
```

Once you run the above command, you will be asked to provide the path of the configuration backup file. If you do not specify any path, then by default, the backup file is stored in the current working directory.

Running a backup as a scheduled job

Following is an example of running a backup as a scheduled cron job on your FortiSOAR Cloud system or external Secure Message Exchange that will run at 12:30 am every day. You can schedule the backup process based on your requirements.

Add the cron job to run at 12:30 a.m. every day as follows:

```
$ sudo crontab -e
30 00 * * * csadm db --backup <backup_dir_path>
```

Once the backup process is successfully completed, the final `DR_BACKUP_<FortiSOARCloud_version>_timestamp.tgz` file is located in the directory where the backup files are created. It would be the same directory that you have specified when you ran the `csadm db --backup <backup_dir_path>` command. The `DR_BACKUP_<FortiSOARCloud_version>_timestamp.tgz` file includes the timestamp of when the backup was created.

The `DR_BACKUP_<FortiSOARCloud_version>_timestamp.tgz` file includes all the backup files. You can run the following command to check the contents of the `DR_BACKUP_<FortiSOARCloud_version>_timestamp.tgz` file:

```
# tar -tvf <DR_BACKUP_<FortiSOARCloud_version>_timestamp.tgz>
```

Restoring data

1. Move the backup file to the new FortiSOAR Cloud VM.
2. SSH to the new FortiSOAR Cloud VM and login as a *root* user.
3. To restore the data, type the following command:

```
# csadm db --restore <backup_file_path>
```

[<backup_file_path>] is the directory where you have saved the backed-up files. Note that the backup process, by default, stores the backup in a locally saved file: `/home/csadmin/db_backup/DR_BACKUP_<yyyymmdd_hhmmss>.tgz`

Important: Once you have restored FortiSOAR Cloud, you are required to reinstall the license for this FortiSOAR Cloud instance. To reinstall the license, click the **Retry Sync** button on the UI.

Troubleshooting

Migration of FortiSOAR Cloud MSSP setup fails with the Secure Message Exchange Invalid credentials or certificate error

A FortiSOAR Cloud MSSP setup that you want to migrate by backing up your FortiSOAR Cloud instance and then restoring it on a new instance fails with the Secure Message Exchange (SME) "Invalid credentials or certificate" error.

Resolution

This issue occurs as the hostname and certificate from the original backup overwrites the hostname and certificate of the new FortiSOAR Cloud instance/account.

1. Use the FortiSOAR Cloud UI to change the name of the embedded SME.
2. SSH to your new FortiSOAR Cloud instance and run the following command:
`csadm secure-message-exchange update-exchange-event-listener-certs`

Upgrading FortiSOAR Cloud

Fortinet offers a managed upgrade service for FortiSOAR Cloud customers to simplify and streamline the upgrade process. You can request the following types of upgrades:

- [Upgrade the release of your FortiSOAR Cloud instance](#)
- [Expand resources for your FortiSOAR Cloud instance](#)


Upgrading your FortiSOAR Cloud instance

You can request a FortiSOAR Cloud instance upgrade using either of the following methods:

- [Using the FortiSOAR Cloud portal](#)
- [Opening a Support ticket](#)

Upgrading your FortiSOAR Cloud instance using the FortiSOAR Cloud portal

1. Log into the FortiSOAR Cloud Portal and navigate to your FortiSOAR Cloud instance page.
2. On the Manage Instance page, click the **Initiate Upgrade Request** button in the Upgrade section:



3. Clicking **Initiate Upgrade Request** opens the Create Upgrade Request form, where you will need to verify or provide the following details:
 - a. Account Name (Read Only): Pre-populated and read-only based on the logged-in account.
 - b. Account Email ID (Read Only): Pre-populated and read-only based on the logged-in account.
 - c. Primary Account ID (Read Only): Pre-populated and read-only based on the logged-in account.
 - d. Type of Deployment (Enterprise, Multitenant, Cluster): Select the appropriate deployment type based on your requirements:
 - **Enterprise:** Standalone instances with license type set to 'Enterprise'.
 - **Multitenant:** Instances with license type set to 'multitenant'.
 - **Cluster:** Instances that are part of a HA cluster.

NOTES:

 - For a high availability (HA) cluster contains instances whose license type is set to 'multitenant', select 'Multitenant.'
 - If your instance is part of a cluster, submit separate upgrade requests for each system in the cluster.
 - e. Upgrade Path: Specify the upgrade path from the supported options.
 - f. Instance ID (Read Only): Pre-populated and read-only based on the current instance.
4. After completing the form, click the **Submit Upgrade Request** button. This will display a pop-up with the upgrade details based on your inputs. Submitting the form will send an email to the Fortinet support team, who will create a support ticket on your

behalf and contact you to complete the upgrade. You can view your submitted requests in the 'Upgrade' section of your Manage Instance page.

Upgrading your FortiSOAR Cloud instance by opening a Support ticket

1. Create a support ticket for upgrade. The ticket must include the following information:
 - a. Account Name
 - b. Account Email ID
 - c. Primary Account ID
 - d. Type of Deployment: Specify the appropriate deployment type based on your requirements, from the following options:
 - **Enterprise:** Standalone instances with license type set to 'Enterprise'.
 - **Multitenant:** Instances with license type set to 'multitenant'.
 - **Cluster:** Instances that are part of a HA cluster.**NOTES:**
 - For a high availability (HA) cluster contains instances whose license type is set to 'multitenant', select 'Multitenant.'
 - If your instance is part of a cluster, submit separate upgrade requests for each system in the cluster.
 - e. Upgrade Path: Specify the upgrade path from the supported options
 - f. Instance ID
2. The Support team will contact you to complete the upgrade process. Once completed, you will receive a notification, and the ticket will be closed.

Expanding resources for your FortiSOAR Cloud instance

If you need to expand the resources for your FortiSOAR Cloud instance, you can purchase additional resources. The SKU provides 1000 GB storage, 8 GB RAM and 4 vCPUs. After purchasing the SKU for additional resources, follow these steps:

1. Register the contract for the extra resources on the Support portal.
2. Create a Support ticket for resource expansion. The ticket must include the following information:
 - a. Account ID
 - b. Service Region
 - c. Instance ID
 - d. Serial Number
3. The Support team will manage the resource expansion process. Once completed, you will receive a notification, and the ticket will be closed.

Appendix A - Supported Regions

The following provides a list of ingress and egress IP addresses for FortiSOAR Cloud. You can use this list in access control lists to allow access to internal applications from FortiSOAR Cloud only.

Region	Data Center	Security ingress	Security egress
North America	Burnaby, Canada	160.223.172.26	160.223.172.16/28
North America	Dallas, United States	154.52.5.160	154.52.9.20
Europe	Frankfurt, Germany	154.52.2.165	194.69.174.8



www.fortinet.com

Copyright© 2025 Fortinet, Inc. All rights reserved. Fortinet®, FortiGate®, FortiCare® and FortiGuard®, and certain other marks are registered trademarks of Fortinet, Inc., and other Fortinet names herein may also be registered and/or common law trademarks of Fortinet. All other product or company names may be trademarks of their respective owners. Performance and other metrics contained herein were attained in internal lab tests under ideal conditions, and actual performance and other results may vary. Network variables, different network environments and other conditions may affect performance results. Nothing herein represents any binding commitment by Fortinet, and Fortinet disclaims all warranties, whether express or implied, except to the extent Fortinet enters a binding written contract, signed by Fortinet's Chief Legal Officer, with a purchaser that expressly warrants that the identified product will perform according to certain expressly-identified performance metrics and, in such event, only the specific performance metrics expressly identified in such binding written contract shall be binding on Fortinet. For absolute clarity, any such warranty will be limited to performance in the same ideal conditions as in Fortinet's internal lab tests. Fortinet disclaims in full any covenants, representations, and guarantees pursuant hereto, whether express or implied. Fortinet reserves the right to change, modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.