



# FortiManager - Deploying on AliCloud

Version 6.0



#### FORTINET DOCUMENT LIBRARY

https://docs.fortinet.com

#### **FORTINET VIDEO GUIDE**

https://video.fortinet.com

### **FORTINET BLOG**

https://blog.fortinet.com

### **CUSTOMER SERVICE & SUPPORT**

https://support.fortinet.com

### **FORTINET TRAINING & CERTIFICATION PROGRAM**

https://www.fortinet.com/support-and-training/training.html

### **NSE INSTITUTE**

https://training.fortinet.com

### **FORTIGUARD CENTER**

https://fortiguard.com/

### **END USER LICENSE AGREEMENT**

https://www.fortinet.com/doc/legal/EULA.pdf

#### **FEEDBACK**

Email: techdoc@fortinet.com



July 22, 2019 FortiManager 6.0 Deploying on AliCloud 02-600-000000-20190722

# TABLE OF CONTENTS

Obtaining the Deployment Image	4
Uploading the FortiManager Installer to AliCloud	5
Configuring Virtual Private Cloud	8
Creating the FortiManager deployment image	10
Creating security groups	12
Creating an instance	15
Connecting to the FortiManager VM	20
Change Log	21

# Obtaining the Deployment Image


## To obtain the deployment image:

- 1. Go to the Fortinet support site (https://support.fortinet.com/) and log in.
- 2. Navigate to *Download* > *VM Images*.
- 3. Under Select Product, select FortiManager.
- 4. Under Select Platform, select AliCloud.
- 5. Download the deployment package file.


# Uploading the FortiManager Installer to AliCloud

## To upload the FortiManager installer to AliCloud:


- 1. Log into Alibaba Cloud.
- 2. Go to Console > Object Storage Service.




3. Click Create Bucket.




**4.** Configure the settings for the bucket and click *OK*.



- 5. Click the newly created bucket.
- 6. Click Files.
- 7. Click Upload.
- **8.** Drag and drop the VM file to the bucket.




9. Click the uploaded file and copy the URL.




# **Configuring Virtual Private Cloud**

## To configure Virtual Private Cloud:

1. Go to Virtual Private Cloud. Click Create VPC.



2. Enter a name for the VPC. Configure the settings as required and click OK.




# Creating the FortiManager deployment image


The following procedure is applicable only if you are uploading a custom image. To deploy FortiManager from the Marketplace directly, go to Creating an instance on page 15.

#### To create the FortiManager deployment image:

1. Go to Snapshot and Images > Custom Images.



- 2. Click Import Image. Configure the settings in the Import Image screen. Configure the following settings:
  - OSS Object Address paste the URL from step 9 in Uploading the FortiManager Installer to AliCloud on page 5 into OSS Object Address.
  - Image Name specify a name for the image.
  - Operating System select Linux.
  - System Disk Size select the minimum disk size as 40 GB.
  - System Architecture select x86\_64.
  - Platform select Other Linux.
  - Image Format select QCOW2.




### 3. Click OK.

# Creating security groups


### To create security groups:

- 1. Go to Elastic Compute Service > Network and Security.
- 2. Click Security Groups.
- 3. Click Create Security Group.




Creating security groups 13


4. Configure the security group and click OK.



5. Click Create Rules Now.




6. Click Add Security Group Rule.



Creating security groups 14

7. Configure the settings as per your network infrastructure and click OK.




FortiManager can be deployed in the following ways:


- Go to *Alibaba Cloud* > *Marketplace* and choose FortiManager. Click *Choose Your Plan* and continue from step 2 described below.
- Create a deployment image as described in Creating the FortiManager deployment image on page 10 and follow the steps below.

#### To create an instance:


1. Go to Elastic Computer Service > Instances, and click Create Instance.




2. Select the Billing Method, Region, and Instance Type.




3. Select the *Image* uploaded in Creating the FortiManager deployment image on page 10. If you are deploying FortiManager from the Marketplace, the image is selected automatically. Specify the storage. Create a *System Disk* and a *Data Disk*. Click *Next*.




**4.** In *Network*, select the VPC and the Switch created in Configuring Virtual Private Cloud on page 8. In *Network Billing Method*, select *Assign Public IP*. Select the Security Group created in Creating security groups on page 12. Click *Next*.




**5.** Add tags and select a *Deployment Set*. This step is optional. Click *Preview*.




6. Add tags and select a Deployment Set. This step is optional. Click Preview.



7. Review the configuration, set an Automatic Release if required, and accept the Terms of Service



8. Click Create Instance. The instance takes about 1 to 5 minutes to be created.



# Connecting to the FortiManager VM

To connect to the FortiManager VM, you need the public IP address.

The default username is admin and the default password is the AliCloud instance ID, which is represented as a number that can be found after locating the instance in AliCloud console.

### To connect to the FortiManager VM:

- 1. Click the FortiManager instance, and view details to get the public IP address.
- 2. Locate the instance ID and copy it to the clipboard.
- 3. In a browser, go to the public IP address for the FortiManager instance.
- **4.** Enter the following information, and press Enter:
  - · Login: admin
  - Password: Paste the instance ID from the clipboard.

You are logged into the FortiManager GUI.

**5.** Change your password by following the prompts.

# **Change Log**

Date	Change Description
2019-05-01	Initial release.





Copyright© 2019 Fortinet, Inc. All rights reserved. Fortinet®, FortiGate®, FortiGate® and FortiGuard®, and certain other marks are registered trademarks of Fortinet, Inc., in the U.S. and other jurisdictions, and other Fortinet names herein may also be registered and/or common law trademarks of Fortinet. All other product or company names may be trademarks of their respective owners. Performance and other metrics contained herein were attained in internal lab tests under ideal conditions, and actual performance and other results may vary. Network variables, different network environments and other conditions may affect performance results. Nothing herein represents any binding commitment by Fortinet, and Fortinet disclaims all warranties, whether express or implied, except to the extent Fortinet enters a binding written contract, signed by Fortinet's General Counsel, with a purchaser that expressly warrants that the identified product will perform according to certain expressly-identified performance metrics and, in such event, only the specific performance metrics expressly identified in such binding written contract shall be binding on Fortinet. For absolute clarity, any such warranty will be limited to performance in the same ideal conditions as in Fortinet's internal lab tests. In no event does Fortinet make any commitment related to future deliverables, features or development, and circumstances may change such that any forward-looking statements herein are not accurate. Fortinet disclaims in full any covenants, representations, and guarantees pursuant hereto, whether express or implied. Fortinet reserves the right to change, modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.