

Cloud Deployment Guide

FortiAnalyzer 7.4.x



FORTINET DOCUMENT LIBRARY

<https://docs.fortinet.com>

FORTINET VIDEO LIBRARY

<https://video.fortinet.com>

FORTINET BLOG

<https://blog.fortinet.com>

CUSTOMER SERVICE & SUPPORT

<https://support.fortinet.com>

FORTINET TRAINING & CERTIFICATION PROGRAM

<https://www.fortinet.com/training-certification>

FORTINET TRAINING INSTITUTE

<https://training.fortinet.com>

FORTIGUARD LABS

<https://www.fortiguard.com>

END USER LICENSE AGREEMENT

<https://www.fortinet.com/doc/legal/EULA.pdf>

FEEDBACK

Email: techdoc@fortinet.com



January 2nd, 2026

FortiAnalyzer 7.4.x Cloud Deployment Guide

05-74-843405-20260102

TABLE OF CONTENTS

| | |
|---|-----------|
| Change Log | 4 |
| Introduction | 5 |
| Requirements | 5 |
| Licensing | 6 |
| Deploying FortiAnalyzer Cloud | 8 |
| Checking requirements and licenses | 8 |
| Deploying a FortiAnalyzer Cloud instance | 9 |
| Configuring FortiOS | 11 |
| Configuring FortiClient EMS/FortiEndpoint | 12 |
| Configuring FortiMail | 14 |
| Configuring FortiWeb | 15 |
| Using FortiAnalyzer Cloud | 19 |
| Accessing your FortiAnalyzer Cloud instance | 19 |
| Access FortiAnalyzer Cloud through FortiCloud | 19 |
| Upgrading firmware from the instance | 20 |
| Identifying the public IP address | 20 |
| Using the FortiAnalyzer Cloud toolbar | 21 |
| Service | 21 |
| Support | 22 |
| Notifications | 22 |
| Account | 22 |
| Privacy and notification preferences | 23 |
| Access Settings | 24 |
| Email Notifications | 24 |
| Enabling managed SOC service from FortiAnalyzer Cloud | 25 |
| Configure log buffer cache size | 27 |
| Using the FortiAnalyzer Cloud & Service portal | 29 |
| Viewing the FortiAnalyzer Cloud portal | 29 |
| Providing feedback | 31 |
| Using account services | 33 |
| Adding a secondary account | 33 |
| Modifying a secondary account | 35 |
| Supporting IAM users and IAM API users | 35 |
| Adding IAM users | 35 |
| Adding API users | 38 |
| Supporting external IdP users | 39 |
| Using multiple roles with external IdP users | 39 |

Change Log

| Date | Change Description |
|------------|---|
| 2023-09-19 | Initial release. |
| 2023-01-30 | Initial release of FortiAnalyzer Cloud 7.4.2. |
| 2024-02-28 | Updated Introduction on page 5 and Accessing your FortiAnalyzer Cloud instance on page 19 . |
| 2024-04-22 | Updated Requirements on page 5 . |
| 2024-06-06 | Initial release of FortiAnalyzer Cloud 7.4.3. |
| 2024-06-28 | Added Privacy and notification preferences on page 23 |
| 2024-07-02 | Added Using multiple roles with external IdP users on page 39 . |
| 2024-09-27 | Initial release of FortiAnalyzer Cloud 7.4.4. |
| 2024-10-18 | Initial release of FortiAnalyzer Cloud 7.4.5. |
| 2025-01-24 | Initial release of FortiAnalyzer Cloud 7.4.6. |
| 2025-04-15 | Updated Introduction on page 5 . |
| 2025-06-16 | Initial release of FortiAnalyzer Cloud 7.4.7. |
| 2025-07-24 | Updated Enabling managed SOC service from FortiAnalyzer Cloud on page 25 . |
| 2025-08-05 | Updated Supporting external IdP users on page 39 . |
| 2025-10-14 | Initial release of FortiAnalyzer Cloud 7.4.8. |
| 2026-01-02 | Updated Adding API users on page 38 . |

Introduction

FortiAnalyzer Cloud is a cloud-based logging platform based on FortiAnalyzer.

FortiAnalyzer Cloud is designed for system health monitoring and alerting using Event Logs, Security Logs, and IOC scans. FortiAnalyzer Cloud can receive Traffic, UTM, and other logs from FortiGate devices.

Logging from non-FortiGate devices, such as FortiClient, is supported with a storage add-on license.

Once the FortiGate device or non-FortiGate device has acquired the required license, FortiCloud can be used to create a FortiAnalyzer instance under the user account. You can launch the portal for the cloud-based FortiAnalyzer from FortiCloud, and its URL starts with the User ID.



SSL inspection for *.forticloud.com must be disabled on any upstream FortiGates in order to reach FortiAnalyzer Cloud.

This section includes the following topics:

- [Requirements on page 5](#)
- [Licensing on page 6](#)

Requirements

The following items are required before you can initialize FortiAnalyzer Cloud:

- Internet access
- Browser
- FortiCare/FortiCloud account with Fortinet Technical Support (<https://support.fortinet.com/>)
Create a FortiCloud account if you do not have one.

A primary FortiCloud account is required to deploy FortiAnalyzer Cloud. A primary FortiCloud account can invite other users to launch FortiAnalyzer Cloud as sub users. See [Adding a secondary account on page 33](#).



Only one FortiAnalyzer Cloud instance can be created per FortiCloud account.

- FortiAnalyzer Cloud SOCaaS subscription (optional)

See [Licensing on page 6](#) for further license details.

This entitles you to a fixed daily rate of logging dependent on the FortiGate model:

| Form Factor | Example FortiGate Model | Total daily log limit for FortiAnalyzer-VM v6.4 and later |
|--|--|---|
| Desktop or FGT-VM models with 2 CPU | FortiGate 30 to FortiGate 90 | 200MB/Day |
| 1RU or FGT-VM models with 4 CPU | FortiGate 100 series, FortiGate 600 series, FortiGate 800 series, FortiGate 900 series | 1GB/Day |
| 2 RU and above or FGT-VM models with 8 CPU and above | FortiGate 1000 series and higher | 5GB/Day |



- Logs from non-FortiGate devices, such as FortiClient and FortiMail require additional licensing. See [Licensing on page 6](#) for more information.
- See the FortiAnalyzer Cloud [release notes](#) for more information on supported software versions.

Licensing

License requirements are enforced when you log in to the FortiAnalyzer Cloud & Service portal.

For more information on license SKUs, see the [FortiCloud SaaS Management & Analytics Ordering Guide](#).

Logging from FortiGate

You can add one of the following FortiAnalyzer Cloud subscriptions to enable cloud-based central logging from a FortiGate hardware or VM device:

| License Type | License SKU |
|---|---|
| FortiAnalyzer Cloud: Cloud based central logging and analytics | FC-10-[FortiGate Model/VM Model Code]-585-02-DD |
| FortiAnalyzer Cloud with SOCaaS | FC-10-[FortiGate Model/VM model Code]-464-02-DD |

Logging from FortiEndpoint

The following FortiEndpoint licenses include cloud-based central logging with FortiAnalyzer Cloud:

| DIY Solution | ZERO TRUST CONNECT | PREVENT | XDR | XDR + SOC | Entitled Log Rate |
|--------------|--------------------|---------------|---------------|---------------|-------------------|
| 25-49 | FC1-10-EMS05- | FC1-10-EMS05- | FC1-10-EMS05- | FC1-10-EMS05- | 50 MB/day |

| DIY Solution | ZERO TRUST CONNECT | PREVENT | XDR | XDR + SOC | Entitled Log Rate |
|--------------|-------------------------|-------------------------|-------------------------|-------------------------|-------------------|
| | 1045-02-DD | 1046-02-DD | 1041-02-DD | 1042-02-DD | |
| 50-499 | FC2-10-EMS05-1045-02-DD | FC2-10-EMS05-1046-02-DD | FC2-10-EMS05-1041-02-DD | FC2-10-EMS05-1042-02-DD | 100 MB/day |
| 500-1999 | FC3-10-EMS05-1045-02-DD | FC3-10-EMS05-1046-02-DD | FC3-10-EMS05-1041-02-DD | FC3-10-EMS05-1042-02-DD | 1 GB/day |
| 2000-9999 | FC4-10-EMS05-1045-02-DD | FC4-10-EMS05-1046-02-DD | FC4-10-EMS05-1041-02-DD | FC4-10-EMS05-1042-02-DD | 4 GB/day |
| 10000+ | FC5-10-EMS05-1045-02-DD | FC5-10-EMS05-1046-02-DD | FC5-10-EMS05-1041-02-DD | FC5-10-EMS05-1042-02-DD | 20 GB/day |

For more information on the licenses available for FortiEndpoint, see the [FortiEndpoint Ordering Guide](#).

Logging from FortiWeb

| License Type | License SKU |
|--|--|
| Support for logging from FortiWeb | FC-10-[FortiWeb Model/VM Model Code]-585-02-DD |
| Support for logging from FortiWeb with SOCaaS | FC-10-[FortiWeb Model/VM Model Code]-464-02-DD |

Additional storage licenses, and logging from FortiClient and FortiMail

Additional storage may also be added as required for FortiGate, FortiEndpoint, and FortiWeb logging. Multiple of the same SKU may be combined.

Purchasing any of the Additional Storage licenses below (for example, FC1-10-AZCLD-463-01-DD) also enables FortiAnalyzer Cloud to receive logs from FortiClient and FortiMail in addition to expanding the amount of logs it may store from FortiGates and FortiEndpoint.

| Additional storage | License SKU |
|--------------------|------------------------|
| +5 GB/day | FC1-10-AZCLD-463-01-DD |
| +50 GB/day | FC2-10-AZCLD-463-01-DD |
| +500 GB/day | FC3-10-AZCLD-463-01-DD |

Add-on services

FortiAnalyzer Cloud supports a number of licensed features including *OT Security Service* and *Attack Surface Rating and Compliance*.

For more information on supported add-on services for FortiAnalyzer Cloud, see the [FortiCloud SaaS Management & Analytics Ordering Guide](#).

Deploying FortiAnalyzer Cloud

The section describes how to deploy FortiAnalyzer Cloud. Following is an overview of the process.

To deploy FortiAnalyzer Cloud:

1. Check requirements and licenses on FortiCloud. See [Checking requirements and licenses on page 8](#).
2. On FortiCloud, deploy a FortiAnalyzer Cloud instance. See [Deploying a FortiAnalyzer Cloud instance on page 9](#).
3. (Optional) Upgrade FortiAnalyzer Cloud to the latest available cloud version. See [Upgrading firmware from the instance on page 20](#).
4. On FortiOS or FortiMail, enable logging to FortiAnalyzer Cloud:
 - For FortiOS, see [Configuring FortiOS on page 11](#).
 - For FortiClient EMS and FortiEndpoint, see [Configuring FortiClient EMS/FortiEndpoint on page 12](#).
 - For FortiMail, see [Configuring FortiMail on page 14](#).
 - For FortiWeb, see [Configuring FortiWeb on page 15](#).



At the time of the 7.4 release, FortiAnalyzer Cloud supports new deployments in version 7.2 and upgrades to version 7.4.

Check the latest [FortiAnalyzer Cloud Deployment Guide](#) to see the current FortiAnalyzer Cloud versions available for deployment.

FortiAnalyzer Cloud 7.0.3 or later is required to support logging from non-FortiGate devices.

Checking requirements and licenses

This section explains how to check whether you have the requirements and licenses needed for FortiAnalyzer Cloud.

To check for requirements and license for FortiAnalyzer Cloud:

1. Go to FortiCloud (<https://support.fortinet.com/>), and use your FortiCloud account credentials to log in. The FortiCloud portal is displayed.
2. Ensure that the license for the registered FortiGate units or non-FortiGate units include a FortiAnalyzer Cloud entitlement:
 - a. Go to *Products > Product List*.
 - b. In the *View Options menu*, select *Group by Category*, and click *Apply*.
The *Product List* is displayed by categories, such as *FortiGate*.
 - c. Expand the *FortiGate* category and click on a device to view its details, and confirm that the device *Entitlement* includes FortiAnalyzer Cloud.

3. Deploy the FortiAnalyzer Cloud instance. See [Deploying a FortiAnalyzer Cloud instance on page 9](#).

Deploying a FortiAnalyzer Cloud instance

This section explains how to deploy FortiAnalyzer Cloud. You can select a region, and then deploy the instance of FortiAnalyzer Cloud to the region.

A primary FortiCloud account is required to deploy FortiAnalyzer Cloud. A primary FortiCloud account can invite other users to launch FortiAnalyzer Cloud as sub users. See [Adding a secondary account on page 33](#).

When deploying FortiAnalyzer Cloud to receive logs from non-FortiGate devices, such as FortiClient, a storage add-on license is also required.

Only one FortiAnalyzer Cloud instance can be created per FortiCloud account.



At the time of the 7.4 release, FortiAnalyzer Cloud supports new deployments in version 7.2 and upgrades to version 7.4.


Check the latest [FortiAnalyzer Cloud Deployment Guide](#) to see the current FortiAnalyzer Cloud versions available for deployment.

To deploy a FortiAnalyzer Cloud instance:

1. If not done already, go to FortiCloud (<https://support.fortinet.com/>), and use your FortiCloud account credentials to log in.


The FortiCloud portal is displayed.

2. From the *Services* menu, select *FortiAnalyzer Cloud*.



The *FortiAnalyzer Cloud & Service* portal is displayed.

3. On the *FortiAnalyzer Cloud & Service* portal:
 - a. Select a *Region* for the FortiAnalyzer Cloud instance. In this example, the region is *Canada (Vancouver)*.
 - b. Select a *Time Zone* for the FortiAnalyzer Cloud instance.
4. Click *Submit*.




5. Confirm your selected region and time zone.




6. Click *Submit*.

7. Review and accept the *Terms of Service* and *Privacy Policy*. Privacy settings can be configured in the instance. See [Privacy and notification preferences on page 23](#).

8. FortiAnalyzer Cloud instance is provisioned in a few minutes.



9. Once provisioned, expand the account, and click *Enter* to access the FortiAnalyzer Cloud instance.




10. (Optional) Upgrade FortiAnalyzer Cloud to 7.4.x. See [Upgrading firmware from the instance on page 20](#).
11. Configure FortiOS to work with FortiAnalyzer Cloud. See [Configuring FortiOS on page 11](#).

Configuring FortiOS

This section explains how to enable FortiOS to send logs to FortiAnalyzer Cloud.

To configure FortiOS:


1. In FortiOS, enable FortiAnalyzer Cloud.
 - a. Go to *Security Fabric > Fabric Connectors*, and edit the *Logging and Analytics* card.
 - b. Select the *Cloud Logging* tab, and set the *Type* to *FortiAnalyzerCloud*.
 - c. Configure the remaining settings to your preference, and click *OK*.



2. In the FortiAnalyzer Cloud instance, go to *Device Manager* and authorize the FortiGate. In some cases, FortiAnalyzer automatically authorizes the FortiGate, and you can skip this step. For

example, FortiAnalyzer can automatically authorize a FortiGate when both devices are part of the same FortiCloud account, and the FortiAnalyzer API can verify the serial number and entitlement for the FortiGate with FortiCare. FortiAnalyzer cannot automatically authorize a FortiGate in an HA cluster or in a Security Fabric.

When successfully authorized, the cloud logging status displays as *Enabled* .



Configuring FortiClient EMS/FortiEndpoint

This section explains how to enable FortiClient EMS 7.0.3 and later and FortiEndpoint to send logs to FortiAnalyzer Cloud.

To configure FortiClient EMS:

1. In FortiClient EMS, enable logging to FortiAnalyzer Cloud.
 - a. Go to *Endpoint Profiles > System Settings*.
 - b. Edit the desired profile.
 - c. Under *Log*, enable *Upload Logs to FortiAnalyzer/FortiManager*, and select the types of logs you'd like to send to FortiAnalyzer Cloud.
 - d. In the *IP Address/Hostname* option, enter the fully qualified domain name for the FortiAnalyzer Cloud instance.

Upload UTM Logs

Upload System Event

Upload Security Event

Upload Vulnerability Logs

Upload Event Logs

Send Software Inventory

Send OS Events

Event telemetry interval seconds

IP Address/Hostname

SSL Enabled

Upload Schedule minutes

Log Generation Timeout seconds

Log Retention days

- e. Configure other fields as desired, and save the profile.
2. In the FortiAnalyzer Cloud instance, go to *Device Manager*, and authorize FortiClient EMS. Once FortiClient EMS can reach FortiAnalyzer Cloud, it uploads logs to FortiAnalyzer Cloud as defined by the upload schedule.
3. In FortiAnalyzer Cloud, go to *Log View* to see the log details.

The screenshot shows the FortiAnalyzer Cloud interface. At the top, it displays 'All FortiClient' and a time filter for 'Last 1 Hour' from 09:21:45 to 10:21:44. Below this is a table of logs with columns for #, Date/Time, User, Host Name, Registered to Device, Source IP, Destination IP, and Remote Name. The table contains 13 rows of log entries. A red vertical bar highlights the 'Destination IP' column for rows 7 through 13. To the right of the table is a 'logDetails' panel for the selected log entry (row 13). The details include: Date/Time: 10:09:01; Destination End User ID: 3; Destination Endpoint ID: 101; Destination IP: 192.168.1.6; Destination Port: 47873; Device ID: FCTEMS8821006498; Device IP: 192.168.1.6; Device MAC: 00-15-5d-51-da-44; Device Name: EMSCloud; Device Time: 2022-11-17 10:09:01; Direction: outbound; Event Type: traffic; FortiClient SN: FCT8001811593155; FortiClient Version: 7.0.7.0345; FortiClientEMS Serial: FCTEMS8821006498; FortiGate Serial: N/A; Host Name: DESKTOP-3SH9CE6; Level: info; Log ID: 96900; Message: Traffic log; OS: Microsoft Windows 10 Enterprise; PC Domain: N/A; Policy Name: Default; Protocol: 6; Received: true; Registered to Device: EMSCloud; Remote Name: www.espn.com; Security Action: blocked; Security Event: webfilter; Sent: false; Service: https; Session ID: 1575651575; Site: default; Source IP: 192.168.1.6; Source Name: msedge.exe; Source Port: 7136; Source Product: Microsoft Edge; Sub Type: system; Threat: General Interest - PersonalSport; Time Stamp: 2022-11-17 10:09:01; Type: traffic; UEBA Endpoint ID: 1025; UEBA User ID: CD71D4D064B49F19634DB7; UID: https://www.espn.com/; User: Douglas Kephart; User Initiated: 0.

| # | Date/Time | User | Host Name | Registered to Device | Source IP | Destination IP | Remote Name |
|----|-----------|----------------|-----------------|----------------------|-------------|----------------|--------------|
| 1 | 10:09:01 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 16 | www.espn.com |
| 2 | 10:09:01 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 16 | www.espn.com |
| 3 | 10:09:01 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 16 | www.espn.com |
| 4 | 10:09:01 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 16 | www.espn.com |
| 5 | 10:09:01 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 16 | www.espn.com |
| 6 | 10:09:01 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 16 | www.espn.com |
| 7 | 10:08:49 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |
| 8 | 10:08:49 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |
| 9 | 10:08:49 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |
| 10 | 10:08:49 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |
| 11 | 10:08:49 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |
| 12 | 10:08:49 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |
| 13 | 10:07:33 | Douglas Kep... | DESKTOP-3SH9CE6 | EMSCloud | 192.168.1.6 | 79.136 | www.goal.com |

Total logs for analytics: 7 days 13 hours. 50 Items per page. 1 of 0.003 Second

Configuring FortiMail


This section explains how to enable FortiMail 7.2.0 and later to send logs to FortiAnalyzer Cloud.

To configure FortiMail:

1. In FortiMail, enable logging to FortiAnalyzer Cloud.

- a. Go to *Log & Report > Log Setting*.
- b. On the *FortiAnalyzer Cloud* tab, toggle on the *Enable* option, and click *Apply*.

As long as FortiMail has the correct license registered with FortiCare, a connection is established with FortiAnalyzer Cloud.




2. In the FortiAnalyzer Cloud instance, go to *Device Manager*, and authorize FortiMail.



After FortiMail is authorized, FortiAnalyzer Cloud can start receiving logs.

3. In FortiAnalyzer Cloud, go to *Log View* to see the logs.



Configuring FortiWeb

FortiWeb supports FortiAnalyzer Cloud, enabling users to store and analyze FortiWeb logs in the cloud.

A valid FortiAnalyzer Cloud (FAZ Cloud) license entitlement and a FortiAnalyzer Cloud storage license are required for log transmission. Upon license expiration, FortiWeb ceases log forwarding, and FortiAnalyzer Cloud rejects incoming logs.


Before configuring FortiAnalyzer Cloud on FortiWeb, verify that the FortiAnalyzer Cloud license is active to ensure proper connectivity and log forwarding. You can check the license status directly from the FortiWeb Dashboard to confirm whether the service is enabled and valid.

FortiWeb must be registered to the same FortiCloud account as FortiAnalyzer Cloud.


For more information on enabling logging from FortiWeb, see the [FortiWeb Administration Guide](#).

To configure FortiWeb logging to FortiAnalyzer Cloud:


1. On the FortiWeb *Dashboard* > *Status* page, upload the license file which includes the FortiAnalyzer Cloud entitlement.
Once the license file is uploaded, FortiWeb will reboot.



2. From the FortiWeb *Dashboard* > *Status* page, you can view the FortiAnalyzer Cloud (FAZCloud) license status in the Licenses widget.



If a SOCaaS license is also added it will also appear with a green checkmark in the licenses lists.




3. On FortiAnalyzer Cloud, go to Device Manager.


FortiWeb will be automatically added and authenticated to FortiAnalyzer Cloud. You can alternatively manually add the FortiWeb device by entering its serial number in the *Add Device* wizard.

To configure a log policy on FortiWeb:


1. On FortiWeb, go to *Log&Report > Log Policy > FortiAnalyzer Policy*. Click *Create New*.




2. Enter a name for the policy and click *OK*.
3. Click *Create New* to open a slide window. Enable *FAZCloud*, and click *OK*.



4. In *Log&Report > Log Config > Global Log Settings*, enable *FortiAnalyzer* and select the *Log Level*, *FortiAnalyzer Policy*, and *Log Type*.



5. Click *Apply*.
6. On FortiAnalyzer Cloud, view FortiWeb logs under *Log View > Logs*.



Using FortiAnalyzer Cloud

After you have deployed FortiAnalyzer Cloud and configured FortiOS, you are ready to use the instance. Using FortiAnalyzer Cloud is similar to using FortiAnalyzer.

For information about using FortiAnalyzer and FortiAnalyzer Cloud, see the [FortiAnalyzer 7.2.1 Administration Guide](#).

This section includes the following topics that are specific to using FortiAnalyzer Cloud:

- [Accessing your FortiAnalyzer Cloud instance on page 19](#)
- [Upgrading firmware from the instance on page 20](#)
- [Identifying the public IP address on page 20](#)
- [Using the FortiAnalyzer Cloud toolbar on page 21](#)
- [Enabling managed SOC service from FortiAnalyzer Cloud on page 25](#)

Accessing your FortiAnalyzer Cloud instance

After deploying one or more FortiAnalyzer Cloud instances, you can access the instances through one of the methods below:


1. Go to <https://fortianalyzer.forticloud.com>. After authentication, you are redirected to your own FortiAnalyzer Cloud instance.
2. Go directly to your instance using the specific URL for your instance (e.g. https://://{account_id}. {region}. fortianalyzer. forticloud. com). You can obtain your instance's URL from your browser's address bar once you have accessed FortiAnalyzer Cloud through one of the previous methods.
3. Access FortiAnalyzer Cloud through FortiCloud. See [Access FortiAnalyzer Cloud through FortiCloud on page 19](#).

Access FortiAnalyzer Cloud through FortiCloud

To access FortiAnalyzer Cloud through FortiCloud:


1. Go to FortiCloud (<https://support.fortinet.com/>), and use your FortiCloud account credentials to log in. The FortiCloud portal is displayed.

- From the *Services* menu, select *FortiAnalyzer Cloud* under *Cloud Management*.



You are automatically logged in to your FortiAnalyzer instance.

- You can navigate between accounts or return to the FortiAnalyzer Cloud portal using the options in the FortiAnalyzer Cloud toolbar. See [Using the FortiAnalyzer Cloud toolbar](#) on page 21.



Upgrading firmware from the instance

For information about upgrading firmware, see the [FortiAnalyzer Cloud Release Notes](#).

Identifying the public IP address

You can use the FortiAnalyzer Cloud CLI to determine the public IP address for FortiAnalyzer Cloud.

To determine the public IP address:

1. Access the instance. See [Accessing your FortiAnalyzer Cloud instance on page 19](#).
2. Open the CLI console by clicking the CLI option from the FortiAnalyzer Cloud toolbar. See [Using the FortiAnalyzer Cloud toolbar on page 21](#).
3. In the CLI console, run the following commands:


```
diagnose debug enable
diagnose test application vmd 20
173.243.137.11
```

In this example, the public IP address for FortiAnalyzer Cloud is 173.243.137.11. You can use the public IP address to set up connections with third-party services, such as LDAP or AWS Management Portal for vCenter.

Using the FortiAnalyzer Cloud toolbar


You can access FortiCloud services and support links from the FortiAnalyzer Cloud toolbar.

The FortiAnalyzer toolbar includes the following dropdown menus:

- [Service on page 21](#)
- [Support on page 22](#)
- [Notifications on page 22](#)
- [Account on page 22](#)


Service

The Service dropdown includes FortiCloud services (for example, IAM and Asset Management) and other cloud portals.




Support

The support dropdown includes downloads, resources, and FortiCare support links.



Notifications

Click the notification icon  to open the notification drawer and view and interact with notifications for FortiAnalyzer Cloud.




Account

The account dropdown includes links and services related to your FortiCloud account and the FortiAnalyzer instance. Available options include the following:

| | |
|---------------------------------|---|
| Account | Your account ID. |
| Username | Your current username. |
| API and CLI | Open the API User or CLI pane. |
| Help Content | Links for Online Help, Basic Setup Videos, Feedback, Privacy Policy, Release Notes, and Terms of Service. |
| FortiCloud Account Links | FortiCloud account links including My Account, Security Credentials, Subscriptions, Return to Portal, ChangeProfile, and Log Out. |
| My Account | Go to the FortiCloud Account Profile page. |


| | |
|------------------------------------|---|
| Security Credentials | Go to the FortiCloud Security Credentials page. |
| Switch Accounts | Switch between available accounts. |
| Return to Portal | Return to the FortiAnalyzer Cloud portal. |
| Change Profile | Change FortiAnalyzer Cloud profile options including avatar and theme. |
| Privacy & Notifications | Click to access the <i>Privacy & Notification</i> menu where you can configure access settings for the FortiCloud team as well as email notification preferences. See Privacy and notification preferences on page 23 . |
| Log Out | Log out of FortiAnalyzer Cloud. |



Privacy and notification preferences

You can configure privacy and notification preferences from within the FortiAnalyzer Cloud instance.

To access your privacy and notification preferences, click your user account dropdown from the FortiAnalyzer Cloud toolbar and click *Privacy & Notification*.



In *Privacy & Notifications*, you can configure the following:

- [Access Settings on page 24](#)
- [Email Notifications on page 24](#)

Access Settings

Access settings determine what level of access Fortinet's cloud operation team has in order to diagnose and perform maintenance on your cloud instance. The following access levels are available:

Privacy & Notifications ✕

Access Settings

- Service Maintenance (Recommended)**
 Fortinet's cloud operation team can access diagnostic data and perform maintenance operations on your cloud instance. However, they only have access to system-level data and do not access personal data like logs, reports, or device configurations. This level ensures the smooth operation of services.
- Full Access**
 Fortinet personnel can access your account with full privileges for support services, including personal data such as logs, reports, and device configurations for troubleshooting.
- No Access**
 The most restrictive control, where Fortinet personnel has no access to your cloud instance. With no access, the cloud operation team cannot access diagnostic data or perform maintenance tasks, and the smooth operation of the service cannot be guaranteed when this level is selected.

Service Maintenance (Recommended)

Fortinet's cloud operation team can access diagnostic data and perform maintenance operations on your cloud instance. However, they only have access to system-level data and do not access personal data like logs, reports, or device configurations. This level ensures the smooth operation of services.

This is the default level of access.

Full Access

Fortinet personnel can access your account with full privileges for support services, including personal data such as logs, reports, and device configurations for troubleshooting.

No Access

The most restrictive control, where Fortinet personnel has no access to your cloud instance. With no access, the cloud operation team cannot access diagnostic data or perform maintenance tasks, and the smooth operation of the service cannot be guaranteed when this level is selected.

Select your preferred access level and click *OK*.

FortiAnalyzer Cloud records changes to access settings in the *Event Log*.

Email Notifications

Email notification preferences can be configured through your FortiAnalyzer instance.

To configure email notification preference:

1. Select your account dropdown from the FortiAnalyzer Cloud toolbar.
2. Select *Privacy & Notifications*.
3. Click the add icon in the *Email Notification* section to configure new email notification preferences.

4. Configure the following:

| Status | Name | Trigger | Email Recipients | Description | Action |
|-------------------------------------|----------------------|----------------------|--|-------------|---|
| <input checked="" type="checkbox"/> | Release notification | New Software Release | <div style="border: 1px solid #ccc; padding: 5px;"> <div style="background-color: #e0e0e0; padding: 2px; margin-bottom: 2px;">User: admin@fortinet.com</div> <div style="text-align: right; padding: 2px;">+</div> </div> | | <input type="checkbox"/> <input type="checkbox"/> |

| | |
|-------------------------|---|
| Status | Toggle the notification preference on or off. Notifications are only sent when the status of the notification preference is enabled. |
| Name | Enter a name for the notification preference. |
| Trigger | Select a trigger condition from the dropdown menu. |
| Email Recipients | Click to add at least one email recipient. You can select IAM/Sub users from the populated list or click the <i>Email Address</i> tab to add additional emails. |
| Description | Add an optional description. |
| Action | You can use the action field to delete a notification preference or create additional notifications preferences. |

5. Click *OK*.

FortiAnalyzer Cloud records changes to email notification preferences in the *Event Log*.

Enabling managed SOC service from FortiAnalyzer Cloud

FortiCloud SOCaaS provides scalable security operations services designed to help you maintain continuous Cyber Awareness and control of your Fortinet Security Fabric network. For more information, see SOCaaS in the [Fortinet Document Library](#).

With a valid license, you can enable the *Managed SOC Service* option in FortiAnalyzer Cloud. When enabling the service, you are redirected to the SOCaaS Portal where you can complete the onboarding process.



- The SOCaaS license includes a complimentary FortiAnalyzer Cloud instance.
- The daily log limit for FortiAnalyzer Cloud is based on the FortiGate model and can be increased by purchasing the FortiAnalyzer Cloud storage add-on licenses. See [Licensing on page 6](#)

To disable the service, submit a service request from the SOC portal.


Prerequisites

Before you configure FortiAnalyzer Cloud to send logs to SOCaaS, ensure the following:


1. You have provisioned the FortiAnalyzer Cloud instance on the region of your choice. See [Deploying a FortiAnalyzer Cloud instance on page 9](#).
2. You have configured the FortiGate to send the entitled device logs to the SOCaaS collection point (FortiAnalyzer Cloud) that will forward the logs. See [Configuring FortiOS on page 11](#).


To configure FortiAnalyzer Cloud:

1. Log in to FortiAnalyzer Cloud.
2. Click on the SOCaaS connection icon at the top of the GUI. A SOCaaS entitlement is required to enable the service.
 - a. Without the correct entitlement, a message is displayed advising you to subscribe your FortiGate devices to the FortiAnalyzer Cloud SOCaaS subscription.




- b. With the correct entitlement, the SOCaaS Onboarding window opens. Click *Onboard Now* to be redirected to the SOCaaS portal where you can complete your onboarding. See the [SOCaaS User Guide](#).





- Once onboarded to SOCaaS, the FortiAnalyzer Cloud SOCaaS icon is no longer clickable and is displayed in green.



- Configure a log buffer cache size that accommodates 24 hours of logs in your FortiAnalyzer Cloud to avoid log dropping in case of abrupt disconnection between your FortiAnalyzer and SOCaaS. See [Configure log buffer cache size on page 27](#).

Configure log buffer cache size

In case of abrupt disconnection between FortiAnalyzer Cloud and SOCaaS, logs will only be cached for the amount of time allowed based on the cache size available. Logs exceeding the available cache storage time are dropped. To avoid log dropping in such cases, we recommended that you configure a log buffer cache size that accommodates 24 hours of logs in FortiAnalyzer Cloud using the following formula:

$$\text{Average Lograte} * 200 * \text{seconds in 1 day (86400)} * 1.2 = \text{Cache Size logfwd}$$

For more information on log forwarding buffers and how log forwarding space allocation works, see the [FortiAnalyzer Administration Guide](#).

Determining the average log rate

The average log rate is the average logs received on your FortiAnalyzer device for 24 hours.

To retrieve average log rate data for your FortiAnalyzer:

1. Go to *Dashboards > Status*.
2. Open the *Settings* for the *Insert Rate vs. Receive Rate* widget.
3. From the *Time Period* dropdown, select *Last 24 Hours*.
4. Click *OK*.
5. View the graph details, and use the peak log rate as the number for the average lograte count. Use this average log rate to calculate the buffer cache size.

The following table provides three example scenarios for calculating the log forwarding buffer cache size for a small, medium, and enterprise business:

| Customer size | Average log rate | Calculation | Buffer cache size |
|---------------|------------------|-----------------------------|-------------------|
| Small | 100 logs/sec | $100 * 200 * 86400 * 1.2$ | 2GB |
| Medium | 1000 logs/sec | $1000 * 200 * 86400 * 1.2$ | 20GB |
| Enterprise | 10000 logs/sec | $10000 * 200 * 86400 * 1.2$ | 200GB |

For more information about sizing, see the [FortiAnalyzer Architecture Guide](#).

6. In the FortiAnalyzer CLI, set the log buffer cache size in GB using the following command

```
config system global
set log-forward-cache-size <integer>
```

7. When prompted, enter Y to confirm the change.

For more information about log forwarding buffers and how log forwarding space allocation works, see [Log forwarding buffer](#).

Using the FortiAnalyzer Cloud & Service portal

After deploying a FortiAnalyzer Cloud instance, you can use the FortiAnalyzer Cloud & Service portal to view and navigate between instances.

- [Viewing the FortiAnalyzer Cloud portal on page 29](#)
- [Providing feedback on page 31](#)


Viewing the FortiAnalyzer Cloud portal

After accessing your FortiAnalyzer Cloud instance, you can navigate to the FortiAnalyzer Cloud portal by opening the toolbar and choosing *Return to Portal*. See [Using the FortiAnalyzer Cloud toolbar on page 21](#).

In the FortiAnalyzer Cloud portal, you can expand each account and view information about the account and any deployed instances.

To view information about instances:

1. Access the portal. See [Accessing your FortiAnalyzer Cloud instance on page 19](#). The FortiAnalyzer Cloud & Service portal is displayed.




2. Expand an account with no instances deployed. The account details are displayed. If it is a primary account, you can provision a new instance. See [Deploying a FortiAnalyzer Cloud instance on page 9](#).

3. Expand an account with deployed instances.

Information about the VM resources and the instance is displayed.

When a firmware upgrade is available, you can click the upgrade icon  to view additional information about the upgrade, choose upgrade immediately, or schedule an upgrade for later. You can also click *Enter* to access the instance.



The following options are displayed:

Dashboard

The top-left includes a dashboard summary of the accounts displayed on the pane:

- *Accounts*: Displays the number of accounts you can access.
- *Alarms*: Displays the number of notifications or alarms that need your attention. Notifications and alarms display in the banner. For alarms, you can also scroll down through the accounts to find an alarm icon on affected accounts.
- *Expiring*: Displays the number of licenses that will expire soon.

Filter

Click to view options to filter by license status and quota/storage alarm.

Refresh

Click to manually retrieve the latest license information from FortiCare and refresh the pane.

Information from FortiCare is also automatically retrieved on a regular interval.

Account Search

Use to search for accounts. In the *Search* box, type search criteria, and press *Enter*. Delete the search criteria, and press *Enter* to display all accounts again.

Accounts summary in table view

Each account displays as a row with the following columns:

- *OU/Account*: The OU/Account this instance is configured for.
- *Account ID*: The account ID.
- *Owner*: The name of the owner.
- *Service Region*: The region where the instance is deployed.
- *# of Device*: The number of devices connected to the instance.
- *Logging Status*: The logging status of connected devices.
- *Logs/Sec*
- *Entitled (GB/Day)*

Expand the pane to view additional information:

- *Service Description*: A short description of the FortiAnalyzer Cloud service.
- *Expiration Date*: The license expiration date.
- *Service Version*: The FortiAnalyzer Cloud version.
- *Enter*: Enter the FortiAnalyzer Cloud instance.
- *API*: Open the *User API Helper* pane with information about API usage for FortiAnalyzer Cloud.

See also [Viewing the FortiAnalyzer Cloud portal on page 29](#).

Providing feedback


Feedback form

In FortiAnalyzer Cloud, you can submit feedback about your cloud experience to Fortinet.

The *Feedback* button is available in the following places:

- The footer on the *FortiAnalyzer Cloud & Service* portal.
- The FortiAnalyzer Cloud portal account dropdown inside the FortiAnalyzer Cloud instance. See [Using the FortiAnalyzer Cloud toolbar on page 21](#).


After clicking the feedback button, you will be presented with a feedback dialog where you can provide comments and suggestions.



The screenshot shows a 'Give Us Your Feedback' dialog box. It features a title bar with a close button (X). The form is divided into three sections: 'Feedback Category' with a dropdown menu currently showing 'Select'; 'Message Details' with a large text area for input; and 'Contact' with a text input field and the label 'If you would like us to contact you, please provide your Email address:'. At the bottom right, there are 'Cancel' and 'Submit' buttons.

FortiAnalyzer Cloud survey

Periodically, a FortiAnalyzer Cloud survey will be shared through the FortiAnalyzer notification menu inviting you to participate in a short survey about your experience with FortiAnalyzer Cloud. When available, you can access this survey through the notifications menu and click *Start Survey* to begin.



Using account services

The FortiCare/FortiCloud account offer several services. This section includes the following topics:

- [Adding a secondary account on page 33](#)
- [Modifying a secondary account on page 35](#)
- [Supporting IAM users and IAM API users on page 35](#)

For information about using FortiCloud portal, see the [FortiCloud Account Services](#) page on the [Fortinet Document Library](#).

Adding a secondary account

Only the primary account holder can create secondary account holders in FortiCloud. The secondary account holder can log in to the same instance. By default, the secondary account holder is assigned the default administrator profile named *Restricted_User*. However, the primary account holder can modify the admin profile for the secondary user.


A secondary account allows the Fortinet support team to troubleshoot the FortiAnalyzer Cloud deployment.




With FortiAnalyzer Cloud 7.0.x and later, you can use the Identity and Access Management (IAM) portal, and you can migrate secondary accounts to the IAM portal. In IAM portal, secondary accounts are called sub users. For information about migrating sub users, see the [Identity & Access Management Guide](#).

To add a secondary account:

1. Go to FortiCloud (<https://support.fortinet.com/>), and use your FortiCloud account credentials to log in.
2. From the top-right corner, click your login name, and select *My Account*.




3. Click *Manage User*.
4. Click the new user icon to add a new user.



- When creating an account for the Fortinet support team, specify an email for the secondary account, and select *Full Access* or *Limit Access*.

A user with full access has the same access level as a primary account user. A user with limited access can only manage the assigned product serial number and will be unable to receive renewal notices or create additional secondary account users.



- Log in to the personal FortiCare portal. Under FortiAnalyzer Cloud section, you will see an account listed as a secondary member.
- Click the entry to expand the view.
- Ask the new user to log in to FortiAnalyzer Cloud.

After the new user logs in to FortiAnalyzer Cloud, the user is displayed on the *FortiAnalyzer Cloud* instance, and the administrator can modify the account. See [Modifying a secondary account on page 35](#).



A secondary account can access the portal thirty days after it expires.

Modifying a secondary account

The new user must log in to FortiAnalyzer Cloud for the account to be displayed in the FortiAnalyzer instance. When new users log in to the account, they are automatically assigned the default administrator profile named *Restricted_User*.

After the new user has logged in to the account, the primary user or a super user can modify the account.

For information about creating a secondary account, see [Adding a secondary account on page 33](#).

To modify a secondary account:

1. Log in to FortiAnalyzer Cloud.
2. Go to *System Settings > Administrators*.
3. Edit the administrator, and assign a different profile.

Supporting IAM users and IAM API users

FortiAnalyzer Cloud 7.0.x and later supports user credentials created in the Identity & Access Management (IAM) portal. On FortiCloud, you can create IAM users and IAM API users, and use them with FortiAnalyzer Cloud.

For more information about using the IAM portal, see the *Identity & Access Management Administration Guide*.


See also [Adding IAM users on page 35](#) and [Adding API users on page 38](#).

Adding IAM users


FortiAnalyzer Cloud supports FortiCloud Identity and Access Management (IAM). You can use the FortiCloud portal to manage users, authentication credentials, and access permissions for FortiAnalyzer Cloud.

To add an IAM user:


1. Go to FortiCloud (<https://support.fortinet.com/>), and log in.
2. From the *Services* menu, select *IAM*.



The IAM portal is displayed.



3. Create a new IAM user.
For more information, see [Adding IAM Users](#) in the *Identity & Access Management (IAM)* guide on the Fortinet Documents Library.
4. Add an IAM user group, and add the user to it.
For more information, see [Adding IAM User Groups](#) in the *Identity & Access Management (IAM)* guide on the Fortinet Documents Library.
5. Generate an IAM user login password.
For more information, see [Generating the password reset link](#) in the *Identity & Access Management (IAM)* guide on the Fortinet Documents Library.
6. The IAM user can use the credentials to log in to FortiCloud.



After logging in to FortiCloud, the IAM user has access to *FortiAnalyzer Cloud & Service* portal.

7. Enter the FortiAnalyzer Cloud instance, and go to *System Settings > Administrators* to view the IAM user.

FortiCloud IAM User Permissions

See the table below for an explanation of how each of the FortiCloud user permissions are associated with a FortiAnalyzer admin profile:

| FortiCloud User Permission | Associated FortiManager Admin Profile |
|----------------------------|---|
| Admin | Assigned to the <i>Super_User</i> admin profile. |
| Read-Write | Assigned to the <i>Standard_User</i> admin profile. |
| Read-Only | Assigned to the <i>Restricted_User</i> admin profile. |
| Custom | <p><i>Custom</i> users are assigned to the <i>Restricted_User</i> admin profile the first time they log in.</p> <p>A <i>Super_User</i> administrator can assign a new or existing FortiManager admin profile to the user. The new admin profile will be applied to the user when they next log in to FortiAnalyzer Cloud.</p> |

You cannot change the FortiAnalyzer Cloud admin profiles assigned to users using the *Admin*, *Read-Write*, or *Read-Only* FortiCloud user permissions.

Adding API users

API users can access FortiCloud services, including FortiAnalyzer Cloud, through the API.

In order to send API requests to FortiAnalyzer Cloud, you must first obtain an access token from FortiCloud using OAuth 2.0. You can use the access token to generate a session ID which is required to send an JSON API request to FortiAnalyzer.

To use the FortiAnalyzer Cloud API:

1. Create an API user in FortiCloud and download your API credentials. See [Adding an API user](#) in the FortiCloud Account Services documentation for instructions on how to add API users.
2. Obtain an access token from FortiCloud using your credentials. See [Accessing FortiAPIs - Authentication and authorization](#) for information on authentication and authorization for FortiAPIs.
3. Use the access token to get a FortiAnalyzer Cloud API session ID using the `https://<FortiAnalyzer_cloud_url>/p/forticloud_jsonrpc_login/` endpoint.

| | |
|-------------------------|--|
| HTTP Method | POST |
| Endpoint | <code>https://<FortiAnalyzer_cloud_url>/p/forticloud_jsonrpc_login/</code> |
| Request Body | <pre>{ "access_token": "<access token obtained in step 2>" }</pre> |
| Response example | <pre>{ "session": "ykF3W6G8CfZv+xecsZBC00n6P0TEbs0*****" }</pre> |

4. Send API requests to the `https://<FortiAnalyzer_cloud_url>/jsonrpc` endpoint with the session included in the body.

For example:

| | |
|---------------------|---|
| HTTP Method | POST |
| Endpoint | <code>https://<FortiAnalyzer_cloud_url>/jsonrpc</code> |
| Request Body | <pre>{ "method": "get", "params": [{ "url": "/sys/status" }], "id": 1, "verbose": 1, "session": "ykF3W6G8CfZv+xecsZBC00n6P0TEbs0*****", }</pre> |



The FortiAnalyzer Cloud API uses session-based authentication. The number of simultaneous API sessions allowed for an API user is controlled by the user's max login setting. By default, this setting is set to 20.

```
config system admin user
  edit <user>
    set login-max 20
```

Supporting external IdP users

External IdP user support enables users to log into FortiAnalyzer Cloud with their company-provided user credentials using a third-party SAML identity provider.

For more information on managing external IdP roles and users for cloud products, see the [FortiCloud Identity & Access Management \(IAM\) user guide](#).

Using multiple roles with external IdP users

For more information on external IdP users for FortiCloud, see [External IdP roles](#).

Logging in as an external IdP user with multiple roles:


1. When logging in as an IdP user that has multiple roles, the account selection page is displayed allowing users to select which instance to access.

External IdP users can have multiple roles assigned to a single FortiAnalyzer Cloud instance.


The screenshot shows a user interface for logging in. On the left, there is a 'Welcome Back!' message with 'FEDERATED LOGIN' and 'fazcloud_fac' details. The user's name is 'idp-multi1'. On the right, a 'Select a Role to Proceed' dialog box is open, displaying a table of roles. The table has columns for 'ACCOUNT ID', 'COMPANY', and 'ROLE NAME'. The roles listed are 'ldp_admin' and 'ldp_readwrite' for various account IDs under the company 'Faz'.

| ACCOUNT ID | COMPANY | ROLE NAME |
|------------|---------|---------------|
| 1691225 | Faz | ldp_admin |
| 1691225 | Faz | ldp_custom |
| 1691225 | Faz | ldp_readwrite |
| 1691226 | Faz | ldp_admin |
| 1691226 | Faz | ldp_custom |
| 1691228 | Faz | ldp_admin |
| 1691228 | Faz | ldp_readwrite |

2. After selecting an instance and role, the portal will use the associated role for the login.




3. Click *Switch Roles* or *Return To Portal* in the FortiAnalyzer Cloud toolbar to return to the FortiAnalyzer Cloud role selection page. On the role selection page, you can select another account and role.




Logging in as an external IdP user with multiple roles in an Organizational Unit:


1. When logging in as an external IdP user with multiple roles in an Organizational Unit (OU), the account selection page is displayed allowing you to select an instance, role, and OU.




2. After selecting an instance, the portal will use the selected role for the login.



3. OU information is displayed with the instance role information.



4. Click *Switch Roles* or *Return To Portal* to return to the FortiAnalyzer Cloud role selection page. On the role selection page, you can select another role or OU to use for login.



Make a Selection to Proceed

Search an Account

- 1691225 | idp_admin_ou | FAZ-Cloud-Root
1471930/OrgRoot/541864
 - faz (Current Account)
1691225/faz01@faz.ca | idp_admin_ou
- Sub-Level-1-FAZ-Cloud
1471933
 - faz
1691226/faz02@faz.ca | idp_admin_ou
 - Sub-Level-2-FAZ-Cloud
1471934
- 1691225 | idp_readwrite_ou | FAZ-Cloud-Root
1471930/OrgRoot/541865
- 1691225 | idp_readonly_ou | FAZ-Cloud-Root
1471930/OrgRoot/541866
- 1691225 | idp_custom_res_ou | FAZ-Cloud-Root
1471930/OrgRoot/542009
- 1691225 | idp_custom_match_ou | FAZ-Cloud-Root
1471930/OrgRoot/542010
- 1691228 | idp_admin_ou | Root-OU-2
1478198/OrgRoot/542011
- 1691228 | idp_readwrite_ou | Root-OU-2
1478198/OrgRoot/542012



www.fortinet.com

Copyright © 2026 Fortinet, Inc. All rights reserved. Fortinet®, FortiGate®, FortiCare® and FortiGuard®, and certain other marks are registered trademarks of Fortinet, Inc., and other Fortinet names herein may also be registered and/or common law trademarks of Fortinet. All other product or company names may be trademarks of their respective owners. Performance and other metrics contained herein were attained in internal lab tests under ideal conditions, and actual performance and other results may vary. Network variables, different network environments and other conditions may affect performance results. Nothing herein represents any binding commitment by Fortinet, and Fortinet disclaims all warranties, whether express or implied, except to the extent Fortinet enters a binding written contract, signed by Fortinet's Chief Legal Officer, with a purchaser that expressly warrants that the identified product will perform according to certain expressly-identified performance metrics and, in such event, only the specific performance metrics expressly identified in such binding written contract shall be binding on Fortinet. For absolute clarity, any such warranty will be limited to performance in the same ideal conditions as in Fortinet's internal lab tests. Fortinet disclaims in full any covenants, representations, and guarantees pursuant hereto, whether express or implied. Fortinet reserves the right to change, modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.