

FORTINET DOCUMENT LIBRARY

https://docs.fortinet.com

FORTINET VIDEO GUIDE

https://video.fortinet.com

FORTINET BLOG

https://blog.fortinet.com

CUSTOMER SERVICE & SUPPORT

https://support.fortinet.com

FORTINET TRAINING & CERTIFICATION PROGRAM

https://www.fortinet.com/training-certification

NSE INSTITUTE

https://training.fortinet.com

FORTIGUARD CENTER

https://www.fortiguard.com

END USER LICENSE AGREEMENT

https://www.fortinet.com/doc/legal/EULA.pdf

FEEDBACK

Email: techdoc@fortinet.com



January, 2023 FortiSOAR 7.3.1 Connectors Guide 00-400-000000-20201228

TABLE OF CONTENTS

| Change Log | 4 |
|--|----------|
| Introduction to connectors | 5 |
| Connector Store | 5 |
| Installing or importing and configuring a connector in FortiSOAR | <u>C</u> |
| Installing or Updating a FortiSOAR connector using the CLI | 16 |
| Working with connectors | 17 |
| How the connector framework verifies the server certificate when it is self-signed | 19 |
| Role-based Access Control for connector actions | |
| Restricting specific connector actions to specific roles | |
| Defining the ownership of a connector's configuration | |
| Troubleshooting | |
| Troubleshooting connector installation issues | |
| Troubleshooting connector usage issues | |
| Building your own connector | |
| Building a connector using the Connector Wizard | |
| Editing a connector Debugging connectors | |
| Writing a custom connector manually | |
| Connector Template Directory Structure | |
| Importing a connector into FortiSOAR | |
| Reimporting a connector | |
| Check_Health function | |
| Add connector operation to a playbook | |
| Configuring a connector to return a response | |
| Updating a connector configuration using the update_connnector_config() function | |
| Configuring a custom connector to support data ingestion | |
| Building your own Pluggable Enrichment Playbook | |
| FortiSOAR Connector SDK | 67 |
| Data Ingestion | 68 |
| Modes of Data Ingestion | 68 |
| Permissions required for using the Data Ingestion Wizard | 69 |
| Data Ingestion Wizard | |
| Process of ingesting data using the Data Ingestion Wizard | |
| Notes for Data Ingestion | |
| Troubleshooting | 80 |
| The Fetch Data screen in case of IMAP displays the ERROR :: create failed: | ~~ |
| [ALREADYEXISTS] Folder name error | 80 |
| ingestion configurations | 81 |
| | |

Change Log

| Date | Change Description |
|------------|--------------------------|
| 2023-01-24 | Initial release of 7.3.1 |

Introduction to connectors

Connectors are used to send and retrieve data from various third-party sources. Using connectors, you can connect to external cyber security tools and perform various automated interactions using FortiSOAR™ playbooks.

FortiSOAR has already developed several connectors that can be used to integrate with many external cyber security tools like SIEMs, such as Splunk, and Ticketing systems such as Jira. Connector-specific documentation that is included with each connector covers the process of installing, configuring, and using these connectors. You can see a list of published connectors on the Fortinet Support Site.

FortiSOAR also provides you with several pre-installed connectors or built-ins that you can use within FortiSOAR playbooks, as a connector step, and perform automated operations. For more information on FortiSOAR Built-in connectors, see the "FortiSOAR Built-in connectors" article.



From FortiSOAR release 7.3.1 onwards, integrations are run using the fsr-integrations user instead of the nginx user. Therefore, code snippets that try to write on a file system that is outside /opt/cyops-integrations or /tmp might be impacted and you also need to ensure appropriate permissions have been given to the fsr-integrations user. Writing on file systems using code snippets outside /tmp is highly discouraged.

You can write a custom connector that can retrieve data from custom sources. You can then use the connector either standalone or within FortiSOAR playbooks and perform automated operations. You can write a custom connector manually, or you can use the FortiSOAR Connector SDK to develop your custom connector. For more information on writing custom connectors, see the Building your own connector chapter.

Use the Connector Store (Content Hub) in the FortiSOAR UI to easily view, search, install, update, and uninstall connectors that are part of the FortiSOAR repository. You can also specify connector configuration using a jinja variable that contains the connector configuration name.



In Release 7.2.0, the Connector navigation take you to the Content Hub with the relevant 'Connectors' filter selected for browsing ease.

Connector Store

Use the Connector Store to easily view, search, install, upgrade, and uninstall connectors that are part of the FortiSOAR repository. Therefore, you can now perform these operations using the FortiSOAR UI instead of the required CLI access. The Content Hub contains all out-of-the-box reference material and product add-ons such as connectors, widgets, and solution packs; whereas the Connector Store has been filtered to display only Connectors.




You must ensure that repo.fortisoar.fortinet.com is reachable from your FortiSOAR instance. Otherwise, you will see a blank page when you click **Content Hub** or **Automation** > **Connectors** in the left navigation.

Following are the permissions that you must be assigned to perform operations on connectors:

- To work with connectors, i.e., view the connectors listed in the Content Hub and changes made to the Content Hub, you must be assigned a role that has a minimum of Read access on the Application, Connectors, Playbooks, and Content Hub modules, a minimum of Create, Read, Update permissions on the Solution Packs module.
- To install a connector from the Content Hub or to upload a connector to the Content Hub you must be assigned a role that has a minimum of Read permission on the Security module.
- Apart from the above, to work with connectors, you need appropriate permissions on the Connectors and Playbooks modules. For example, to install a connector or create a new custom connector, you must be assigned a role that has a minimum of Create and Read access on the Connectors module and Read access on the Playbooks modules, or to upgrade or configure a connector, you must be assigned a role that has a minimum of Update and Read access on the Connectors module and Read access on the Playbooks module.


To open the **Connector Store**, go to **Automation > Connectors**, or to go to **Content Hub**, click **Content Hub** in the left menu. The **Connector Store** is filtered to display only connectors, whereas the **Content Hub** displays all the add-ons. In this chapter the screenshots included are from the **Content Hub** page; similar screens are displayed on the **Connector Store** page.

The **Discover** tab displays all the add-ons, i.e., Connectors, Widgets, and Solution Packs, available in the Content Hub. Use the Filter panel to filter the connectors by clicking the > arrow in the **Content Type** list and then selecting **Connectors**:




You can search for a connector by its name in the **Search** field and sort the content alphabetically (A-Z) or by date. Using the **Filters** panel, you can filter the connectors displayed in all the tabs based on varied criteria. For more information on Content Hub, see the *Content Hub* chapter in the "User Guide.' Connectors that are installed appear with a tick on their card. For example, the Active Directory connector in the above image.

To install a connector, click that connector's card, for example, AbuseIPDB, which opens a popup with the connector name:




The connector popup contains details such as the name and version of the connector, whether the connector is certified or not, who is the publisher of the connector, and the link to the connector documentation. The **Summary** tab contains a brief description of the connector, and the **Contents** tab contains a list of actions the connector can perform.

Click **Install** in the connector name popup to begin the installation of the connector after confirmation, as shown in the following image:




Once installation is complete, FortiSOAR displays the "Connector Installed successfully" message, and the connector gets added to the **Manage** page. After installing the connector, you must configure the connector by entering the





You can also configure the connector on the **Manage** page by clicking the connector name card, which will also display the same connector popup. For more information, see the Installing or importing and configuring a connector in FortiSOAR section.

Some connectors have dependencies on additional python packages, which if not installed would hamper the functioning of the connector. By default, the dependencies are resolved from pypi.org and repo.fortisoar.fortinet.com. Dependencies could fail to install due to reasons such as the blocking of users' pypi or not having the latest deps repository on repo.fortisoar.fortinet.com. In such cases where the connectors get installed but the dependencies fail to install, FortiSOAR displays a **Connector Dependencies Failed To Install** message on the connector configuration popup as shown in the following image:



You can try to reinstall the dependencies by clicking the Install link.

Dependencies of connectors that are not installed from FortiSOAR Content Hub might fail to install even after a retry since the dependencies for such connectors are not present in the FortiSOAR repository. In such cases, you can download the dependencies from pypi.org and install the dependencies using the information present in https://pip.pypa.io/en/latest/user_guide/#installing-from-local-packages.

To install a package in FortiSOAR, use the following command:

sudo -u fsr-integrations /opt/cyops-integrations/.env/bin/pip install <package>

Installing or importing and configuring a connector in FortiSOAR

Use the Connector Store to install and configure connectors in FortiSOAR.

To install a connector, you must be assigned a role that has a minimum of Create access to the Connectors module. To configure connectors into FortiSOAR, you must be assigned a role that has a minimum of Update access to the Connectors module.

The following procedure describes how to install and configure connector using Connector Store:

- 1. Log on to FortiSOAR.
- 2. On the left navigation pane, click **Connector Store > Discover**.


 On the Discover page, you will see all the connectors, both which are installed and which are not installed.

Installed connectors appear with a with a tick on their card. You can search for a connector by its name in the **Search** box and sort the connectors either alphabetically or by date.

To install a connector, click that connector's card, which opens a popup with the connector name on which click **Install**. This process is described in the Connector Store section.

Once installation is complete, FortiSOAR displays the "Connector Installed successfully" message, and the connector gets added to the **Manage** page in the 'Active' state; however, you can change the state of the connector from active to inactive by toggling the **ACTIVE** button.


To import a connector (.tgz) file into FortiSOAR, click the **Manage** tab and on the Manage page, click **Upload > Upload Connector** to display the **Upload Connector** popup as shown in the following image:




You can drag and drop the connector .tgz file onto the popup or browse to the .tgz file to install the connector in FortiSOAR. If you have an existing version of the connector on your system, then you can click the **Replace existing version** checkbox, to replace that version of the connector.

You must check that all the connector dependencies are available or install the additional dependencies to ensure that the connector functions as expected.


3. To configure a connector, on the Manage page, click the connector card to open the Connector Configuration popup. Enter the required configuration details in the connector configuration popup, as shown in the following image:



Once you add the configuration details in the connector popup and click **Save**, FortiSOAR opens a modal window that displays the progress of the configuration and the status of the health check while saving the connector configuration:



All errors or warnings related to connector configuration, including missing dependencies, invalid configurations, and health check status, are displayed in the modal window:




The health check status and missing dependencies are also displayed on the connector configuration popup. You can choose to try to reinstall the dependencies by clicking the **Install** link that appears alongside the **Connector Dependencies Failed To Install** message on the modal window or the connector configuration popup as described in the Connector Store section.

Note: Once you have installed a connector dependency on a FortiSOAR node using the **Install** link on the connector's Configurations dialog, then that dependency is installed seamlessly on the other nodes of the HA cluster.


Notes on Configuration:

- If you are configuring the connector for the first time, then in the Configuration Name field add a name of the configuration.
 - **Note**: You can add multiple configurations for your connector, therefore, you must add a unique Name for each configuration in the **Configuration Name** field.
- If you have previous versions of a connector and you are configuring a newer version of that connector, with the same configuration parameters, then FortiSOAR fetches the configuration and input parameters of the latest available version of that connector. For example, if you have 1.0.0 and 2.0.0 versions of the Database connector and you are configuring the 2.0.0 version of the Database connector, then while configuring the 2.0.0 version, FortiSOAR will fetch the configuration and input parameters from the 1.0.0 version of the Database connector. You can review the configuration and input parameters, and then decide to change them or leave them unchanged.
- To add a new configuration, click the +Add New Configuration button, and then add the name of the configuration and specify the configuration parameters. You can click the < Back to Configuration Selection






• If you want to update an existing configuration, then select the configuration from the **Select Configuration** drop-down list and update the configuration parameters. If there is only one configuration, then that



configuration will be selected automatically.

- Check the Mark As Default Configuration option to make the selected configuration, the default configuration
 of this connector, on the particular FortiSOAR instance. This connector will point to this configuration by
 default, and it is important that you mark at least one configuration as default, so that the connector uses that
 configuration for performing actions.
 - **Important**: In the case of the SMTP connector, you must ensure that this option is selected for the configuration that is to be used for sending system notifications.
- The password type fields in FortiSOAR include encryption and decryption. Passwords are encrypted before
 saving them into the database and decrypted when they are used in actions. In case of an upgrade, connectors
 that are already installed will work with stored passwords. If your administrator has configured an external vault
 to securely store your organization's sensitive data and credentials, then you can use the Dynamic Values
 dialog to enter the credentials for your connector as shown in the following image:



For information on Dynamic Values, see the *Dynamic Values* chapter in the "Playbooks Guide." For information on Password Vault, see the *Security Management* chapter in the "Administration Guide."

- You can also define the ownership of connector configurations by setting the visibility of a connector's
 configuration to 'Private'. For more information, see the Defining the ownership of a connector's configuration
 section.
- You can configure connectors for the current FortiSOAR node, an agent, which is used to remotely run actions, or both. For more information on agents and how to run remote actions using agents, see the Segmented Network support in FortiSOAR chapter in the "Administration Guide." You can configure on the current node (Self) or on a remote Agent node (Agent) by clicking the Self, which is the default, or Agent buttons besides Target. You can configure multiple configurations for a connector on both the current node and the agent node. To configure and execute connector actions on the "Agent" node, click Agent, and from the Select Agent drop-down list select the agent on which you want to run the connector actions. If there is only one agent installed, then that agent will be selected automatically.
- Connectors also include a Verify SSL field, that specifies whether the SSL certificate for the server is to be
 verified or not. By default, this option is set as True. For more information, see How the connector framework
 verifies the server certificate when it's self-signed.
- To view the documentation associated with a connector, click the **Documentation** link on the top-right corner
 of the connector configuration pane.

Points to be considered for connector configurations while upgrading to a newer version of the connector

If you are upgrading a connector to a newer version, you must be assigned a role that has a minimum of Upgrade access to the Connectors module. For example, if you are upgrading the Symantec Security Analytics connector version from v1.0.0 to v2.0.0, then keep a note of the following points:

- Existing (older) connector configuration fields retain their value, i.e., the value from the older configuration will be displayed in the configuration pane of the newer connector version. New connector configuration field(s), if any, will be added to the connector configuration pane.
- If the newly added configuration field is mandatory, and FortiSOAR has specified its default value (in the info.json file of the connector), then the configuration pane of the newer version of the connector will contain the default value for this configuration field. For more information on the connector framework and the info.json file, see the Building your own connector chapter.

For information on common connector framework issues, see the *Common connector framework errors* section in the Debugging common playbook and connector issues article present in the Fortinet Knowledge Base.

- If the newly added configuration field is mandatory, and FortiSOAR has not specified its default value (in the info.json file of the connector), then the configuration pane of the newer version of the connector will contain a blank value for this configuration field. If you also do not specify a value for this mandatory configuration field, then the connector configuration pane will display **Partially Configured**, and an error will also be displayed in the Playbook Execution Log. For more information on the Playbook Execution Log, see the *Debugging and Optimizing Playbooks* chapter in the "Playbooks Guide."
- If the field type of a mandatory configuration field is changed from the older version to the newer version, for example from a text field to a drop-down list, then the value of that field will *not* be retrieved from the older version. However, if FortiSOAR has specified its default value (in the info.json file of the connector), then that value will be displayed for this configuration field in the configuration pane of the newer version of the connector. If however FortiSOAR has not defined the default value and you also do not specify a value for this mandatory configuration field, then the configuration pane of the newer version of the connector will contain a blank value for this configuration field, and the connector configuration pane will display **Partially Configured**. An error will also be displayed in the Playbook Execution Log. For more information on the Playbook Execution Log, see the *Debugging and Optimizing Playbooks* chapter in the "Playbooks Guide."
- If the newly added configuration field is optional, and FortiSOAR has specified its default value (in the info.json file of the connector), then the configuration pane of the newer version of the connector will contain the default value for this configuration field. If there is no default value is set, then its value is set as blank.

Installing or Updating a FortiSOAR connector using the CLI

All connectors published by FortiSOAR are delivered using a FortiSOAR repository. Use the Connector Store to easily install, update and install connectors that are part of the FortiSOAR repository.



The recommended way to install a connector is by using the Connector Store.

You could also set up your FortiSOAR repository and use the yum command to install connectors as a root user:

yum install cyops-connector-<connectorname>



After you install a connector using the yum command the new connector is not reflected until you refresh the Connectors page.

To update a FortiSOAR-published connector use the following command:

yum update cyops-connector-<connectorname>

To remove a FortiSOAR-published connector use the following command:

yum remove cyops-connector-<connectorname>



If you delete a FortiSOAR-published connector using the Connector page in FortiSOAR then you cannot reinstall the RPM of the same connector because the RPM of the connector does not get deleted. Therefore, to remove a FortiSOAR-published connector, you must use the yum remove cyops-connector-<connectorName> command.

Some of the connectors have dependencies on additional python packages. During connector installation, these dependencies are also installed using pip. The default pip settings point to the pypi.python.org repository for downloading these packages. We have also added an alternate repository on repo.fortisoar.fortinet.com to host the connector dependencies. If your instance restricts access to pypi.python.org, the installer fallbacks to this alternate repository for installing the dependencies. However, the connector installation might take longer if there are multiple dependencies since it first tries to fetch each of those from pypi.python.org. In such a case, it is recommended to switch to repo.fortisoar.fortinet.com as the main repository for the python packages also. You can switch the main repository to repo.fortisoar.fortinet.com so by editing the pip.conf file located at: /opt/cyops-

integrations/.env/pip.conf as follows:

index-url=https://repo.fortisoar.fortinet.com/connectors/deps/simple/. If some dependencies fail while installing the connector, you can use the connector configuration popup to try and reinstall the failed dependencies as described in the Connector Store section.


You can also change other relevant pip settings such as altering the timeout or retry count setting. See https://pip.pypa.io/en/stable/user_guide/#config-file for a listing of the relevant pip settings. For example, to increase the timeout value add the following in the pip.conf file: timeout = 60.

For information on installing connectors on an FSR agent, see the *Segmented Network Support* chapter in the "Administration Guide."

Working with connectors


On the Manage page, you will see the list of installed connectors in the card view. You can perform the following operations on this page:

You can search for a connector by its name in the Search box and sort the connectors either alphabetically or by
date. Also, when you select Connectors as the Content Type by default, Non Configured connectors are
displayed in the Manage tab. You can select Configured from the drop-down to view the configured connectors.




Similarly, you can filter the installed connectors that have an upgraded version, by selecting Upgrade Available
from the second drop-down list. For example, version 5.0.0 of the Fortinet FortiGate connector is installed on your
system and Fortinet has released a newer version of this connector, then you will see the Fortinet FortiGate
connector filtered by the Upgrade Available filter, and you can also see Update Available link on the connector's

card:



To update a connector, click the **Update Available** link on the connector card. When you click on a connector that has an updated version, you will see a **'What's new?'** section on the configuration page, besides the **Update to <version number>** button. Clicking the **What's New?** link displays the highlights of the new version, which you can view to understand what you can expect when you upgrade your connector version. Click the **Update to <version number>** button to upgrade your connector.



You can perform the following operations on the connector configuration popup (click the connector card in the Manage page to open the connector configuration popup) of a configured connector:

• To perform a Health Check by clicking the **Refresh** icon that is present in the Health Check bar. The Health Check checks if the configuration parameters you have specified are correct and if connectivity can be established to the specified server, endpoint, or API. If all the details are correct and the connectivity to the server can be established, then on the Connectors page, **Available** is displayed in the health check dialog. If any or all the details are incorrect or if the connectivity to the server cannot be established then on the Connectors page, **Disconnected** is displayed in the health check dialog.

- To modify a connector according to your requirements, click the Edit on the connector configuration popup.
 However, to edit a connector, you must make a local copy of the connector and then make the changes in the same, and then you can save and publish the connector as defined in the Building your own connector chapter.
- To uninstall a connector, click the **Uninstall** button, in the connector configuration popup. FortiSOAR displays a Confirmation dialog, click Confirm to uninstall the connector. FortiSOAR displays the "Connector uninstalled successfully" message and the connector is removed from the Manage page. To uninstall a connector, you must be assigned a role that has a minimum of Delete access on the Connectors module.
- To export the .tgz file of the connector, click the **Export** button.
- To view the list of actions that can be performed by the connector and the playbook file that is bundled with the
 connector, click the Actions & Playbooks tab. Clicking the 'Actions' option on this tab, you can also restrict specific
 connector actions to specific roles, i.e., users with only those roles would be able to perform that action. For more
 information, see the Restricting specific connector actions to specific roles section,
- To view the list of agents on which the connector is installed, click the **Agents** tab. For more information on agents and how to run remote actions using agents, see the *Segmented Network support in FortiSOAR* chapter in the "Administration Guide."

How the connector framework verifies the server certificate when it is self-signed

The connector framework is explained in the Building your own connector chapter.

All connector calls are made by the python requests library reading the certificate from <code>/opt/cyops-integrations/.env/lib/python3.9/site-packages/certifi/cacert.pem</code>. Therefore, for any connector, when you set <code>verify_ssl</code> to <code>true</code>, and it's a self-signed cert, then the <code>cacert</code> must be appended to this file. If it's a chain of trust, then you must add the entire chain in the <code>pem</code> format. You must also ensure that the server address added in the connector configuration matches the CN in the certificate.



A . \ker file has the path to a PEM encoded file containing the private key. A . pem file has the path to a PEM encoded file containing the certificate (or certificate chain) that will be presented when requested.

If you are using the HTTPS proxy for external connections, then you must ensure that the proxy certificate is added here also, if the <code>Verify SSL</code> is set to true in the connector configuration.

Some commands that you can use to get the pem certificate chain:

```
\begin{tabular}{ll} $\#$ openssl $s\_client$ -connect $\{$HOSTNAME\}$: $\{$PORT\}$ -showcerts \\ $OR$ \\ \end{tabular}
```

If you have the certificate already in a .crt, .cer, .der format, then you need to convert to the pem format: # openssl x509 -inform der -in certificate.cer -out certificate.pem

Role-based Access Control for connector actions

From version 7.0.0 onwards, FortiSOAR introduces Role-based Access Control (RBAC) for connectors, i.e., 'Connector Administrators', i.e., users with Connector Read and Update permissions and Security Read permission can allow

access to only certain teams or users, based on roles, to perform certain connector actions. For example, the administrator might want to allow a "Block IP" action to be performed by only certain teams or users in the organization.

The ownership of connector configurations can also be defined, by marking the connector configuration as 'Private'; thereby, controlling who can view and execute that particular connector configuration.




You must configure access control for connector configurations and actions separately for the tenant nodes. Access control for connector configurations and actions cannot be configured from the master.


Restricting specific connector actions to specific roles

By default, all users and roles with appropriate permissions, as defined in the Connector Store section, can view and execute all the connector actions; however, connector administrators can restrict specific actions to specific roles as follows:


- 1. Log on to FortiSOAR.
- 2. On the left navigation pane, click **Connector Store > Manage**.
- 3. Select the connector whose connector actions you want to restrict to certain users, based on the roles or specific set of roles that have been assigned to open the Connector Configurations page.
- 4. Click the Actions & Playbooks tab:




5. From the **Actions** tab, in the row that contains the action that you want to restrict, click the **Assign Role(s) to Action** icon to display the Assign Role(s) to Action dialog:



6. Select the roles that would be able to perform this action and then click **OK**. Once a particular action is assigned to specific roles, you can see a **Roles Assigned** bar in that action's role, which specifies the roles that the users should be assigned to perform that connector action:



Therefore, in this case, if there are users who are not assigned the 'Full App Permissions', 'Playbook Administrator' or 'SOC Analyst' role, and if they try to invoke this action directly on a record, they will be unable to run that action as the action will be disabled:



Notes:

- When a connector is upgraded to a higher version, if there are any roles defined for any connector action in the previous version of the connector, those roles are carried forwarded to the upgraded version.
- The Playbook designer displays all the connector actions irrespective of the roles of the user creating the playbook. Also, while executing a connector action from the playbook, FortiSOAR does not perform any role check. You can create a playbook as a 'Private' playbook to restrict access. For more information, see the "Playbooks Guide."
- When a connector action is being executed directly on a record, the roles of the logged-in user will be matched against the roles permitted for the action.

Defining the ownership of a connector's configuration


The ownership of connector configurations can also be defined by setting the visibility of a connector's configuration to 'Private'. By default, the connector configuration is set to 'Public', i.e., it can be viewed by anyone who has appropriate permissions, as defined in the Connector Store section. By setting a connector's configuration to 'Private', you are assigning ownership of that connector configuration to particular teams and thereby only allowing the assigned team owners the right to view and execute that particular connector configuration.



You must configure access control for connector configurations and actions separately for the tenant nodes. Access control for connector configurations and actions cannot be configured from the master.

To set the visibility of connector configurations to 'Private' to restrict the teams who can view and execute that particular connector configuration, do the following:


- 1. Log on to FortiSOAR.
- 2. On the left navigation pane, click Automation > Connectors > Installed.
- 3. Select the connector whose configuration you want to set to 'Private', i.e., whose configuration you want to restrict to certain teams. By default, connector configurations are set to 'Public'.



4. To mark a connector configuration as 'Private', click the **Private** button beside the **Visibility** parameter:

- 5. To assign the connector configuration to a particular team, once you have clicked **Private**, click the **Teams** (icon to display the Assign Owners dialog.
- 6. In the Assign Owners dialog, you will see that the logged-in user's teams are assigned ownership, by default.


 Click the **Red Cross** beside the teams whose ownership you want to remove, and select the teams that you want to



configure as owners for this connector configuration from the **Owners** drop-down list and then click **Assign**:

7. Click Submit to assign ownership of this connector configuration.

Now, in this case, if there are users who are not part of the 'SOC Analysts' team, and if they want to run the actions of the VirusTotal connector on a record, for example, they will observe that the "New Default" configuration will not be visible and only the "Default" configuration is visible:



Therefore, users can see only those connector configurations to which they have access, as is the case with the above example, the 'New Default' configuration is visible only to users that belong to the 'SOC Analysts' team. However, users belonging to teams other than 'SOC Analysts' can execute playbooks containing a connector step with the 'New Default' configuration that has been created by 'SOC Analysts' users.

Troubleshooting



From FortiSOAR release 7.3.0 onwards, PIP dependencies packages for connectors are located at $\protect\prote$

Troubleshooting connector installation issues

Issues uninstalling integrations pip dependencies

This topic uses an example of the tzlocal package and demonstrates uninstalling this package. You can replace tzlocal with the name of the package that you want to uninstall.

Run the following command to uninstall integrations pip dependencies (the tzlocal package):

```
# sudo -u fsr-integrations /opt/cyops-integrations/.env/bin/pip uninstall tzlocal
```

The following message get returned:

```
Found existing installation: tzlocal 4.2
Not uninstalling tzlocal at
/opt/cyops/configs/integrations/packages/lib/python3.9/site-packages, outside
environment /opt/cyops-integrations/.env
Can't uninstall 'tzlocal'. No files were found to uninstall.
#
```

Resolution:

If you want to uninstall the pip (tzlocal) package, do the following:

- 1. Run the following command to find the files that are part of the pip package: find /opt/cyops/configs/integrations/packages/lib/python3.9/site-packages -name tzlocal*
- 2. Manually remove files that are listed as the output of previous 'find' command.

Issues downgrading integrations pip dependencies

Usually, you should not be required to downgrade the integrations pip dependencies; however, if after debugging you require to downgrade, then use the following steps.

Resolution:

Fortinet Inc.

- 1. Remove the pip dependencies files that are already installed.
 For example if you want to downgrade tzlocal, first find the files that are already installed for tzlocal and then remove those files:
 - a. Run the following command to find the files that are part of the pip package (tzlocal): find /opt/cyops/configs/integrations/packages/lib/python3.9/site-packages -name tzlocal*
 - b. Manually remove files that are listed as the output of previous 'find' command.

2. Install the required version using the following command:

sudo -u fsr-integrations /opt/cyops-integrations/.env/bin/pip install
tzlocal==<required-version-here>

Troubleshooting connector usage issues

Handling rounding of large integer values

You might find that fields with large integer values get round-off causing issues while working with connectors. For example, when you submit a URL or file to FortiSandBox, a SID (Session ID) gets created. This session is further used to get job id "JID", using which indicator information can be retrieved. However, due to the large integer values getting rounded-off, FortiSOAR replaces the last four digits of the "JID" to 0000. Due to this you would be unable to retrieve the information for submitted indicator from FortiSandBox. This issue occurs as JavaScript lacks an explicit integer type in JavaScript; and instead represents all numbers in double-precision 64-bit floating-point format as defined by the IEEE 754-2008 standard. Under this standard, very large integers that cannot be exactly represented are automatically rounded. To be precise, the Number type in JavaScript can only safely represent integers between -9007199254740991 (-(253-1)) and 9007199254740991 (253-1). Any integer value that falls out of this range might lose precision.

Resolution

As a workaround to these limitations, large integers can be represented using the 'String' type, i.e., instead of passing integers directly such as, 123456, pass integers in a single quote such as, '123456'. The Twitter API, for example, adds a string version of IDs to objects when responding with JSON. For now, such a large number must be returned as a 'String' in the response to the connector action.

Building your own connector

You can write a custom connector that can retrieve data from custom sources. You can then use the connector either standalone or within FortiSOAR playbooks and perform automated operations. From version 7.0.0, you can create your own connector using the Connector Wizard. You can also write a custom connector manually, or you can use the FortiSOAR Connector SDK to develop your custom connector.

The process of installing, configuring, and using FortiSOAR-provided connectors is defined in the respective connectorspecific documentation.


For permissions required to build a connector, see the Introduction to Connectors chapter.

Building a connector using the Connector Wizard


Use the Connector wizard to create a new connector. You can also edit an existing connector according to your requirements by clicking **Edit** on a connector card in the **Manage** tab.

To create a new connector, do the following:

- 1. Log on to FortiSOAR.
- 2. On the left navigation pane, click Content Hub > Create or Automation > Connectors > Create.
- 3. To create a new connector, click Create > New Connector:




This opens the "Connector Wizard":



Click the Lets's start by defining a connector button to start building your connector.

4. In the Connector Wizard, in the **About Connector** screen, you need to provide the basic details such as name, description, etc. of the connector that you want to create, as well as, upload a logo for the connector, and choose a suitable template for the connector:



You need to add the following details on this screen:

- a. Click the Upload icons buttons to upload large, medium, or small logos for your connector. Clicking the upload button opens the Upload Connector Logo dialog, where you can drag-and-drop your logo, or browse to the logo on your disk and import the logo.
- b. In the Connector Name field, add the name of the connector that you want to create.
 It is a good practice to include both the name of the organization and the name of the product in the connector name, for example, Fortinet FortiSOAR.
- c. In the **API Identifier** field, enter a name that would be used as a variable in the connector code to reference this connector. The variable that you use here can be alphanumeric; however, it should not contain any special characters and it must not start with a number.
 - Also, note that the value that you enter in this field must not match the name of any other connector that is available in the Connector Store or Content Hub. For example, you cannot enter 'virustotal' in this field,

since the VirusTotal connector is available in Content Hub.


Note: You cannot change the 'name' and 'version' of a connector once it is set.

- d. In the Connector Version field, enter the version of the connector in the x.y.z format. For example, 1.0.0. Note: It is recommended that you increase the version number if you are making any changes to an installed connector
- e. (Optional) In the Publisher field, enter the name of your organization as the publisher of this connector. The publisher of the connector is responsible for maintaining and supporting the connector. If you want to keep the connector anonymous, then you can add the "Community" keyword. If this field is left blank, again the connector's publisher is automatically set to "Community". Note: Do not enter "Fortinet" in this field.
- f. In the **Description** field, you can optionally enter information for the connector that you are creating. The Description is displayed on the Connector card on the Connector Store or Content Hub's listing page and enables users to understand more about the Connector.
- g. From the Select Template drop-down list, select the template that you want to apply to the connector that you want to create. Templates are based on the broader category of connectors, for example, Threat Intelligence connectors,

Ticketing connectors, etc. Templates automatically add suggestive actions, configuration details, and other connector details based on the type of connector you want to create, which helps to speed up the development process.

- h. Once you have completed entering all the details, click Save & Continue, to go to the Configuration
- 5. Use the Configuration screen to set up the connector configuration page. If you have specified a template in the About Connector screen, then you will see that some suggestive configuration fields are added based on the selected template, else you will not see any configuration fields and you require to add all the required configuration fields.


If, for example, in the About Connector screen, the Threat Intel is selected from the Select Template drop-down list, then you will see the following Configuration screen:



To add fields to the connector configuration, click + button alongside Fields or click the Add Field link and can easily add properties to that field, like selecting the type of field you want to add such as Text, Integer, Email, etc., and even a sub-type of Text fields such as URL, Filehash, etc., all of which help you in ensuring that the user enters appropriate values in the field. You can also set other properties such as visibility and a default value of the field, whether it is required or not, etc.


Important: You cannot add fields that are named 'name' and 'default' to the connector configuration since 'name' and 'default' are reserved keywords.

To edit existing fields and change their properties, select the field to change the properties and click Apply.



Once you have completed entering all the details, click Save & Continue, to go to the Actions screen.


6. Use the **Actions** screen to set up the connector actions. From version 7.0.2 onwards, you can define the actions that the connector should perform in the form view, instead of having to edit a raw JSON file. If you have specified a template in the **About Connector** screen, then you will see that some suggestive actions are added based on the selected template, else you will not see any actions and you require to add all the required actions to the connector. If, for example, in the **About Connector** screen, the **Threat Intel** is selected from the **Select Template** drop-down list, then you will see the following Actions screen:



To add actions, click the **+ Action** button, to edit an action click the down (**v**) arrow to display the metadata and parameters for the action, and click the **Delete** icon to remove the action. You can also type a keyword in the **Filter Actions** field to filter the actions of the connector.


To add a new operation to the connector, click + Action, and enter the following details for the action:

- a. In the Action Metadata section, enter the following metadata details for the action:
 - i. In the **Title** field, enter a suitable name for the action that would explain the purpose of the action. For example, if you want to perform a lookup for a specific domain, then you can enter *Lookup Domain* in the Title field.
 - **ii.** From the **Select Category** drop-down list, select a suitable category for the action from options such as Investigation, Remediation, Utilities, etc. For example, select *Investigation*.
 - iii. In the Description field, enter a description that explains the action and the utility of the action.
- b. In the Action Parameters section, define the parameters associated with the action. If your action does not need any input parameters to work, you do not need to add any parameters in this section. To add parameters, click the **Add Field** link and define its properties.
 - You need to specify the type of field, its field name and title, and other properties such as visibility and required field or not, a default value of the field, etc.



Once you have completed editing the connector configuration and adding the actions to the connector, click **Save & Create Connector**, which displays the **Summary** screen.

7. On the Summary screen and you can click Open in Code Explorer to edit and test the connector.



The created connector also gets saved in the **Create** tab, from where you also edit the connector. For more information, see the Editing a connector section.


Editing a connector

You can use the connector's code editor interface to edit existing connectors and build new connectors for custom use cases.

To edit an existing connector that is installed on your system, open the **Manage** tab and click the connector card to open the connector popup, and click **Edit**. However, before you can make any changes to an installed connector, you are required to create a local copy of that connector. For example, clicking **Edit** on the *VirusTotal* connector. This displays a Confirm dialog that requires you to clone the connector before making any changes, click **Confirm** to open the Clone dialog, where you should update the connector name, version, and also ensure that you have specified a unique API Identifier and then click **Create**:



Clicking Create opens the code editor interface where you can make the required changes to the connector.




It also saves the cloned connector in the **Create** tab, with the name that is specified in the **API Identifier** field, i.e., 'VirusTotal v2.2.1_dev'.



You cannot change the connector name and API identifier for a connector once it is set.

If you want to edit a custom connector that has been created using the Connector Wizard and not installed from Content Hub, and which has been published (installed), you are not required to clone the connector. Instead, you can choose to either edit, save, and publish the same version of the connector, or choose to add a new version to the connector. For

example, if you click **Edit** on the 'Demo' connector (created using the Connector Wizard), the Edit Connector dialog displays the **Edit** and the **Add Version** options:






If a connector is published and is being used by other users, it is recommended that you add a version to the connector before editing the connector code, so that the changes you make do not cause any issues to existing operations done using the connector.

Once you create a connector using the "Connector Wizard", or if you are editing an installed connector, then those connectors are saved in the **Manage** tab from where you can edit the connector.

To edit a connector, do the following:

1. Open the Manage tab:




In the **Manage** tab, you will see connector cards with their details such as the connector version, the created and the last modified dates, whether the connector is installed or not, etc.

You might see more than one version of the connector if you are working on multiple versions of the connector, and also when you publish a connector a working copy of that version of that installed connector is maintained in the **Manage** tab.

To add a version for the connector, click Add Version, which will again display the Clone Connector dialog.






The files and folders that are present are similar to what is described in the Writing a custom connector manually section. A brief description of these files and folders follows:

• The info.json file contains information about the name and version of the connector, logo image file names, the configuration parameters, the set of functions supported by the connector, and their input parameters. The name of all the fields in the info.json file must be unique.

From version 7.0.2 onwards, you can choose to edit the info.json file in the **Form** view, instead of editing the file in the raw JSON format, by clicking the **Form View** button:



The **Form View** of the info.json file, contains Metadata, Configuration, and Actions information for the connector. Click the down (v) in the respective row to add or edit the information for each of these items.

- Metadata: Contains information about the connector, including the name, version, logo, etc. of the connector.
- Configuration: Contains the configuration parameters for the connector that is used to set up the
 connector configuration page.

- **Actions**: Contains the actions that the connector can perform and its associated Metadata and parameters.
 - For more information on editing these items in the Form View, see the Building a connector using the Connector Wizard section.
- From version 7.0.2 onwards, you can use the connector wizard to add actions to the connector or you can also use the **Form View** of the info.json file. In case you want to manually add an action to a connector, i.e., edit the raw JSON file, then you must add the operation parameters in the info.json file, and this in turn, creates a .py file per operation. Each operation .py file contains the default template format for the operation. Once the info.json is updated with the operation it is mapped in the builtins.py.
- The connector.py file extends the base connector class and implements the check_health and execute functions.


Note: The <code>connector.py</code> template file provides an additional function called <code>dev_execute</code> that can be used during the development phase of the connector. Code changes do not always reflect without a service restart; therefore <code>dev_execute</code> reloads the function definition at every 'execute' call to ensure that the changes made at every save in the code get immediately reflected. You can change the <code>execute</code> function in <code>connector.py</code> as follows to call the <code>dev_execute</code> function instead:

```
def execute(self, config, operations, params, *args, **kwargs):
    return self.dev execute(config, operation, params)
```

However, note that reloading the function at every function call is slow and performance-intensive. So, once the development is complete and the connector is ready to use, you must revert the code to the original. For more information on connector.py, see the connector.py section.

- The images directory contains the connector logo files.
- The **playbook** directory contains the playbook.json file, which contains the playbook collection that you want to include with your connector.
- The requirements.txt file lists the additional python libraries that are required by the connector. However, the connector dependencies are not installed by default when the connector is created. If you want to test the connector that is being developed, you must manually install the connector dependencies.
- The release_notes.md file (present for connectors that have released versions) contains information such as what's new and what's fixed, in a particular release of a connector.
- 3. Apart from the above files, it is recommended that you maintain a file (utils.py) that contains common functions such as DateTime conversion, str to list, etc., which can be used by multiple actions in the connector.
- 4. Edit the existing connector as required, and click Save Changes.
 - The connector is saved in the "Draft" state.


The left-pane of the code editor interface contains the name of the connector along with various icons using which you can perform actions such as creating new files and folders, and also uploading or deleting selected files or folders:




You can also rename connector files and folders or copy its path, by right-clicking the selected file or folder row and selecting **Rename** or **Copy Path**.

You can also perform the following operations on the code editor interface:


- **Code Formatting**: To lint your code automatically and make the code more human-readable and error-free (programming and programming errors), select the entire code in the editor and click the **Format** button.
- Full Screen: To get a better working view and make the editor go full-screen, click the Fullscreen button. To exit the full screen, press ESC.
- **Export**: To export the connector as a .tgz file, click the **Export** button. You might want to import the exported connectors' .tgz file into another system.
- Testing the configuration: While developing a connector, you can perform a health check operation on the connector. Clicking the Test Configuration button opens a dialog containing the specified configuration parameters, where you can input the values, save the configuration, and perform the health check. If the configuration is valid, i.e., the configuration parameters and values specified are correct, then the health check will appear as "Available", else it will appear as "Disconnected".



• **Testing the actions**: You can use the saved configuration for testing connector actions for their output/errors. Clicking the **Test Actions** button displays a list of actions for that connector. Click the action that you want to test to display a dialog containing the input parameters for that action. Enter the values for the input parameters and click **Execute Action** to view the output for that action.



Once the connector action is executed, you can see the formatted output of the action, in a tabular format, as shown in the following image:



- Deleting the Connector: To delete the connector, click the Delete Connector. button.
- 5. Once you have completed making the changes, click Publish Connector to display the Publish Connector dialog:



Click **Publish Only** to publish the connector and make it available on the **Discover** tab for all the users of the system and use it in playbooks or run directly on records. However, a working copy for the same is also maintained in the **Create** tab.

To delete all existing versions of the connector from your system, select the **Delete all existing versions** checkbox.

Removing images of a connector installed from the Content Hub

If you are editing a connector that is part of the Content Hub, for example 'VirusTotal' and you want to remove the images of such a connector, do the following:

- 1. Open the connector in the code editor interface, and click the **images** folder.
- 2. Select the image that you want to delete and then click the **Delete** icon, then click **Delete** on the confirmation dialog.
- 3. In the code editor interface, click info.json and edit the info.json file to remove the file references of the deleted image. For example, if you have deleted the large logo for the connector (large.png), then in the info.json file, remove its reference:

```
"icon large name": "large.png"
```

4. To save your changes, click Save Changes.

Debugging connectors

- You can add logger statements to test your connector's code paths. Use the <code>get_logger</code> utility function to initialize the logger. You can import <code>get_logger</code> from <code>connectors.core.connector</code>, and then declare the logger as <code>logger = get_logger('<connector name>')</code>. Then you can add <code>logger.error('<logger_message>')</code> to the <code>operation.py</code> file that you want to debug.
- If your connector's configuration or action fails, you can check the connector logs. All the connector logs are written to the /var/log/cyops/cyops-integrations/connectors.log file and follow the format: % (asctime) s % (levelname) s % (name) s % (module) s % (funcName) s(): % (message) s

The default log level is WARN, however, you can change it to INFO or DEBUG.

For example, to change the log level to INFO:

Open the /opt/cyops-integrations/integrations/configs/config.ini file and set connector_logger level = 'INFO', and then restart the uwsgi service.

Writing a custom connector manually

Perform the following steps to write a custom connector manually:

- 1. Create a Connector Template Directory Structure with the required files.
- 2. Import the connector into FortiSOAR.
- 3. Check the health of the connector.
- 4. Add a connector operation to a playbook.

Connector Template Directory Structure

Create the following folder structure, with a folder with the connector name at the top and files within it:

connectorname folder

```
--+ playbooks
---+ __init__.py
---+ playbooks.json
--+ connector.py
--+ info.json
--+ images
--+ requirements.txt
--+ packages
---+ package_name>
```



Python 3 is required for developing your connectors.

info.json

The info.json file contains information about the name and version of the connector, logo image file names, the configuration parameters, the set of functions supported by the connector, and their input parameters. The name of all the fields in the info.json file must be unique.



Ensure that the name of the connector in the info.json and the name of the connector folder matches exactly.

You can configure the following parameters, fields, and operations while writing connectors: description of connector and actions, tooltip, placeholder, conditional fields, backward compatibility (using visible_onchange parameter), validation using regex, label, apioperations, and grouping of fields. These parameters are explained in the **Notes** following the sample info.json file.

Following is an example of an info.json file:

```
"name": "sampleConnector",
"label": "sampleConnector",
"description": "sampleConnector connector description",
"publisher": "publisherName",
"cs_approved": true/false,
"cs_compatible": true/false,
"version": "1.0.0",
```

```
"category": "categoryType",
"icon_small_name": "small_icon.jpeg",
"icon_large_name":"large_icon.jpeg",
"configuration": {
  "fields": [
      "title": "fieldname",
      "required": true/false,
      "editable": true/false,
      "visible": true/false,
      "type": "text",
      "description": "text",
      "name": "user",
      "tooltip": "text for the tooltip",
      "placeholder": "placeholder text",
      "validation":{
           "pattern": "regex pattern for validation",
           "patternError": "text for the error message if validation fails"
    } ]
},
"operations": [
    "operation": "function template",
    "title": "Sample Function",
    "description": "description of the operation",
    "category": "categoryType",
    "annotation": "sample annotation",
    "parameters": [{
      "title": "Sample Input1",
      "required": true/false,
      "editable": true/false,
      "visible": true/false,
      "type": "text",
      "name": "input1",
      "description": "text",
      "value": "default value1"
      "tooltip": "text",
    },
      "title": "Sample Input2",
      "required": true/false,
      "editable": true/false,
      "visible": true/false,
      "type": "text",
      "name": "input2",
      "description": "text",
      "tooltip": "text",
      "value": "",
      "options": ["A", "B"],
      "onchange": {
           "A": [{
             "title": "User2",
             "required": true/false,
             "editable": true/false,
             "visible": true/false,
```

```
"visible onchange":false,
           "type": "text",
           "name": "user2",
           "description": "text",
                      "tooltip": "text",
           "value": "admin1"
         }],
         "B": [{
           "title": "User2",
           "required": true/false,
           "editable": true/false,
           "visible": true/false,
           "type": "integer",
           "name": "user2",
           "description": "text",
                      "tooltip": "text",
           "value": 12345
           "title": "Comment1",
           "required": true/false,
           "editable": true/false,
           "visible": true/false,
           "type": "text",
           "name": "comment1",
           "description": "text",
                      "tooltip": "text",
           "placeholder": "Add comment1",
           "value": "",
           "onchange": {
             "placeholder attribute": [{
               "title": "placehoder attribute title",
               "required": true/false,
               "editable": true/false,
               "visible": true/false,
               "type": "checkbox",
               "name": "placehoder attribute name",
               "description": "text",
                           "tooltip": "text",
               "value": false
             }
           ] }
         } ]
   }
 }],
  "enabled": true,
  "output schema": {"key1": "", "key2": []}
},
{
         "operation": "Sample Operation 2",
         "category": "containment",
         "annotation": "sample op",
         "title": "title of the operation",
         "description": "description of the operation",
         "is config required": true/false,
         "parameters": [
             {
```

```
"title": "title of list",
                    "type": "text",
                    "name": "sample list",
                    "required": true/false,
                    "editable": true/false,
                    "visible": true/false,
                    "description": "description of the operation",
                    "tooltip": "text"
       },
                    "type": "label",
                    "label": "label text",
                    "visible": true
       },
                    "title": "title of list",
                    "type": "text",
                    "name": "sample list",
                    "description": "description of the operation",
                    "required": true/false,
                    "editable": true/false,
                    "visible": true/false,
                    "class": "group-element",
                    "tooltip": "text"
       },
                    "title": "title of list",
                    "type": "text",
                    "name": "sample_list",
                    "description": "description of the operation",
                    "required": true/false,
                    "editable": true/false,
                    "visible": true/false,
                    "class": "group-element",
                    "tooltip": "text"
       },
                    "title": "title of list",
                    "type": "text",
                    "name": "sample_list",
                    "description": "description of the operation",
                    "required": true/false,
                    "editable": true/false,
                    "visible": true/false,
                    "class": "group-element last",
                    "tooltip": "text"
      }
      ],
            "enabled": true,
            "output schema": {}
"ingestion supported": true,
"ingestion_modes": [
```

}

]

Notes:

- The version of the connector must be in the **x.y.z** format, for example, **1.0.0**. The version must consist of valid integers, for example, "1.15.125" is a valid version.
- The output_schema defines the keys that are present in the output json on the execution of an operation. The info.json contains some common keys. However, the output json can have additional keys based on the input parameters. You can use these json keys to set the input for subsequent Playbook Steps, using the Dynamic Values. For more information, see the *Dynamic Values* section in "Playbooks."
- To support data ingestion, the "ingestion_supported" key must be set to true. You must also specify the ingestion method(s) that are supported by the connector using the "ingestion_modes" key. FortiSOAR supports the following ingestion methods: "ingestion_modes": ["scheduled", "notification", "app_push"] You can also customize the label of the button that is used to open the 'Data Ingestion Wizard'. By default, the label is set to "Configure Data Ingestion," which might not be appropriate in some cases, where the "Data Ingestion Wizard" must be run per configuration. If you want to change the default label, then add the "launch_name" parameter and its value in the "ingestion_preferences" key in the connector's info.json file. If the "ingestion_preferences" key is not present in the connector's info.json file, then you must first add the "ingestion_preferences" key, and then add the "launch_name" parameter and its value. For example: "ingestion_preferences": {
 "launch_name": "DI Configuration"
- If you want to add online and/or offline documentation for your connector, add the following to your info.json: help_file: "name of pdf file in the connector folder" help online: "link to the online documentation for the connector"
- Input types supported: text, password, checkbox, integer, decimal, datetime, phone, email, file, richtext, json, textarea, image, select, and multiselect.

For select and multiselect, you can provide the list of inputs using the options key. For example,

```
"title": "Sample Field",
    "name": "sample",
    "required": "true",
    "editable": "true",
    "visible": "true",
    "type": "select",
    "options": ["A","B","C"]
}
```

• category and annotation within operations: The category defines the category for the connector that you are adding, and it must be one of the following: investigation, remediation, containment, and miscellaneous. The annotation defines the operation or function that will be performed. An annotation is unique and belongs to only one category, i.e., you must not add an annotation to multiple categories. If you do not define any category in the info.json file, then by default, the annotation is added to the miscellaneous category.

The category name must contain only lower-case alphabets. The annotation name must contain only lower-case

alphabets, underscores, and numbers.

Category and annotations must always come together.

Multiple operations within a connector can use the same annotation.

- description: You can add a description for the connector, which will be visible on the connector page in
 FortiSOAR and you can also add a description for the action or operation, which will be visible on the connector step
 page in the Playbook Designer.
- is_config_required: By default, the is_config_required key is set to true (default), which means that the connector uses the configuration specified in the connector configuration to execute an action. If you set the is_config_required key to false, then configurations are not required to execute an action and in this case, you can use dynamic fields to specify the configurations.

Note: This key is applicable at the action level, i.e., limited to a single action.

- tooltip: You can add the tooltip parameter to any field to display information about that particular field. Note that if you do not want a tooltip against any field, then you must remove the tooltip parameter from that field in the info.json. You must not pass "" or null as values to the tooltip parameter.
- placeholder: You can add the placeholder parameter for text and select fields, which will display placeholders for those fields on the connector step page in the Playbook Designer.
- conditional fields (onchange): You can add the onchange parameter to fields, which you can use to display other fields or subfields conditionally based on the user input for that field. For example:

```
"options": ["Now", "Yesterday"],
"onchange": {
              "Now": [{
                "title": "Comment3",
                "required": true,
                "editable": true,
                "visible": true,
                "type": "text",
                "name": "comment3",
                "value": ""
              "Yesterday": [{
                "title": "Comment4",
                "required": true,
                "editable": true,
                "visible": true,
                "type": "text",
                "name": "comment4",
                "value": ""
              } ]
```

- visible_onchange: For backward compatibility of the connector you can use the visible_onchange parameter for conditional fields (onchange parameter).
 If you set visible_onchange to false, then this field will be hidden in FortiSOAR UI, and if you set visible_onchange to true, or if it is not present for any field, then this field is visible in FortiSOAR UI.
- validation: You can add regex validation to text and textarea fields. You can also add the error that will be displayed in case the validation fails. For example:

```
}
```

• label: You can add the label field to display text on the connector UI. For example:

```
{
"type": "label",
"label": "this is my label",
"visible": true
}
```

• grouping: You can group fields based on your categorization using "class": "group-element". For the last field in the group, use "class": "group-element last".

For example:

```
{
       "operation": "block_applications",
       "parameters": [
              "type": "label",
              "label": "this is my label",
              "visible": true
       },
           {
               "title": "Applications Names (List Format)",
                "type": "text",
                "name": "app list",
                "required": true,
                "editable": true,
                "visible": true,
                "class": "group-element",
                "tooltip": "Block Applications Names (List Format)"
       },
               "title": "Applications Names (List Format)",
               "type": "text",
                "name": "app list",
                "required": true,
                "editable": true,
                "visible": true,
               "class": "group-element last",
              "tooltip": "Block Applications Names (List Format)"
       }
     ]
```

- apiOperations: You can fetch options for the select and multiselect fields from the API that you have defined in your operation. The parameters to this operation will be what users have entered in the configuration of this operation and the target field. apiOperations is not supported for the connector configuration.
 Note: To hide this operation in the from the Actions drop-down list in the Playbook Designer set "visible": false for this operation.
- supports_remote: Some connector actions cannot work when run on agents in a segmented network. Therefore, parameters of those actions must be marked as "supports_remote": False. For example:

```
"title": "Enable abc service",
"name": "abc_service",
"supports remote": False
```

• conditional_output_schema: Support for multi-option or dynamic output schema in connectors. In every operation that requires the dynamic output schema, you must add conditional_output_schema as a key in an array of objects. Each object will contain the condition, which you should add within {{}} and then you must add the corresponding output schema for each condition. It is recommended that you add a default schema, using "condition": "{{true}}", at the end of the defined conditions. The default schema will be used if none of the defined conditions are met.

Notes:

a. If you are using multiple conditions for evaluation such as a combination of && and |||, then you must wrap the whole condition within ().

```
For example, {{ (command === 'ls' || command === 'ssh' )}}
{{ (command === 'ls' && port === 5895 )}}
```

b. If you are using the condition with the checkbox field, add the condition as:

```
{{ checkbox === true}}
```

c. If you are using the condition with the multi-select field, add the condition as:

```
{{multsel.toString() === (['option1','option2']).toString()}}
```

d. If you are using the condition with the json field, add the condition as:

```
{{jsonfieldname === '{\"key\":\"value\"}'}}
For example, {{jsonfieldname === '{\"name\":\"fortinet\"}'}}
```

Important: To support versions earlier than the 4.12.0 release, output_schema will also always be present. Example of a conditional output schema definition:

```
"conditional output schema": [
     {
             "condition": "{{command === 'ls'}}",
             "output schema": {
                  "op result": "",
                  "op status": ""
         },
             "condition": "{{command === 'ssh'}}",
             "output schema": {
                 "result": "",
                 "status": ""
             }
         },
             "condition": "{{true}}",
             "output_schema": {
                  "result default": "",
                  "status": ""
             }
         }
]
```

connector.py

The connector.py class extends the base connector class and implements the <code>check_health</code> and <code>execute</code> functions. Following is a skeleton of this class:

```
from connectors.core.connector import Connector, get_logger
logger = get_logger('<connector_name>')

class Template(Connector):
    def execute(self, config, operation, params, **kwargs):
        supported_operations = {'operation_1': function_template}
        return supported_operations[operation](config, params)

def check_health(self, input):
    return True
```

Notes:

- All imports for the connector files should be relative. For example, if your util.py is parallel to connector.py and you want to import util.py then you must import it as: import .util.
- get_logger is a utility function to initialize the logger. You can import get_logger from connectors.core.connector, and then declare the logger as logger = get_logger('<connector name>'). All the connector logs are written to the /var/log/cyops/cyops-integrations/connectors.log file and follow the format: % (asctime) s % (levelname) s % (name) s % (module) s % (funcName) s(): % (message) s.
- In addition to the execute and check_health functions, the following optional and additional functions are also available:

on_add_config(self, config): Invoked when a new configuration is added to the connector. This is an optional function that can be overridden while setting up a new configuration.

on_update_config(selfself, old_config, new_config): Invoked when a configuration is updated for the connector. This is an optional function that can be overridden while setting up a configuration edit function. on_delete_config(self, config): Invoked when a configuration is deleted from the connector. This is an optional function that can be overridden while setting up a configuration teardown function.

```
\verb"on_activate(self, config): Invoked when a configuration is activated.
```

on deactivate(self, config): Invoked when a configuration is deactivated.

on_teardown(self): Invoked when a configuration is deleted. This is an optional function that can be overridden for dismantling a connector.

You can use these functions to perform specific operations such as starting or stopping services at the relevant events. For example, you can use the <code>on_add_config()</code> function to start and stop a service when a configuration is added.

playbooks.json

The playbook.json file contains any playbook collection that you want to include with your connector. This could be a set of playbooks that demonstrate the usage of your connector.

images

The images directory must have the connector icon files. The 'icon_small_name' and 'icon_large_name' keys in the info.json must match the names of these icon files inside the images folder. Icon files can be in the .jpg or .png formats.

Once you have created all the files, bundle them into a .tgz file. For example, tar -czvf sampleConnector.tgz sampleConnector/.

requirements.txt and packages

If a connector requires additional python libraries, specify the libraries in the requirements.txt file.

If there is a dependency on any custom packages or if your instance does not have internet access to download packages from the internet, you can add the packages to the packages directory in the connector folder.


If the installation of a dependency, then you can install them again by invoking the REST APIs directly. Contact FortiSOAR Support for more details on the APIs.

Importing a connector into FortiSOAR

Use the "Content Hub" or "Connector Store" to install and configure connectors in FortiSOAR 5.0.0 and later. To install a connector, you must be assigned a role that has a minimum of Create access to the Connectors module. To configure connectors into FortiSOAR, you must be assigned a role that has a minimum of Update access to the Connectors module. For more information about the Content Hub, Connector Store, and the process of importing connectors into FortiSOAR, see the Introduction to connectors chapter.

Importing a connector into FortiSOAR prior to release 5.0.0


- 1. Log on to FortiSOAR.
- 2. On the left navigation pane, click Automation > Connectors and click Add Connector.



3. Drag-and-drop the connector package file or click Browse File to import the connector.tgz file. FortiSOAR will prompt you to enter the configuration inputs that you have defined in the info.json file. Note: You can install different versions of a connector, enabling you to reference a specific version of a connector from a playbook. If you want to replace all previous versions of the connector, ensure that you click the Delete all existing versions checkbox while importing the new version of the connector. If you do not click the Delete all existing versions checkbox, then a new version of the connector is added. You must ensure that your playbooks

reference a correct and existing version of the connector.

Following is a sample image:



FortiSOAR displays the Uploading Connector message and then displays the Connector Configuration popup.

4. To configure the connector, enter the required configuration details in the Connector Configuration popup. The configuration details and the details of the connector specified in the info.json file are stored in the FortiSOAR database.

Note: You can add multiple configurations for your connector if you have more than one instance of your third-party server in your environment. You must, therefore, add a unique Name for each configuration.

If you have previous versions of a connector and you are configuring a newer version of that connector, with the same configuration parameters, then FortiSOAR fetches the configuration and input parameters of the latest available version of that connector. For example, if you have 1.0.0, 2.0.0, and 2.3.0 versions of the Fortinet FortiSIEM connector and you are configuring the 2.3.0 version of the Fortinet FortiSIEM connector, then while configuring the 2.3.0 version, FortiSOAR will fetch the configuration and input parameters from the 2.0.0 version of the Fortinet FortiSIEM connector. You can review the configuration and input parameters, and then decide to change them or leave them unchanged.

You can activate or deactivate a configured connector by clicking on the **Activate Connector** or **Deactivate Connector** Link.

You can check the **Mark As Default Configuration** option to make the selected configuration, the default configuration of this connector, on the particular FortiSOAR instance.

The password type fields in FortiSOAR include encryption and decryption. Passwords are encrypted before saving them into the database and decrypted when they are used in actions. In case of an upgrade, connectors that are already installed will work with stored passwords.

5. To save your configuration, click Save.

To view the list of actions that can be performed by the connector, click the **Actions** tab.

To view the playbook file that is bundled with the connector, click the **Playbooks** tab.

You can optionally perform a Health Check by clicking the **Refresh** icon that is present in the Health Check bar. The Health Check checks if the configuration parameters you have specified are correct and if connectivity can be established to the specified server, endpoint, or API.

If all the details are correct and the connectivity to the server can be established, then on the Connectors page, **Available** is displayed in the health check dialog.

If any or all the details are incorrect or if the connectivity to the server cannot be established then on the Connectors page, **Disconnected** is displayed in the health check dialog.

You can also click the **Refresh** icon that is present in the Health Check bar to perform the health check at any time.

Reimporting a connector

After importing a connector, any changes done in the python files of the connector automatically get reflected the next time you run a command on the connector. However, if changes are made in the info.json, then you need to reimport the connector, using the following command, for the updates to take effect:

```
/opt/cyops-integrations/.env/bin/python /opt/cyops-integrations/integrations/manage.py
reimport connector -n <connector name> -cv <connector version> -migrate
```

If you only want to update the info.json changes and not retain the previous connector configuration, then you can omit the -migrate attribute as follows:

```
/opt/cyops-integrations/.env/bin/python /opt/cyops-integrations/integrations/manage.py reimport connector -n <connector name> -cv <connector version>
```

You can also reimport all connectors at a single time using the following command by omitting the -n <connector_name> and -cv <connector_version> attributes as follows:

/opt/cyops-integrations/.env/bin/python /opt/cyops-integrations/integrations/manage.py reimport connector -migrate

Check Health function


The <code>check_health</code> function of the connector is invoked when you click the <code>Refresh</code> icon. This function takes the dictionary of the configuration parameters as the input. For example: { 'url': 'https://xyz.com', 'user': 'admin', 'password': 'password'}.

You must throw the <code>ConnectorError</code> from the function if you want the <code>check_health</code> function to fail in a given scenario, such as issues with connectivity or with the provided credentials. To throw the <code>ConnectorError</code>, you must import it from the <code>connectors.core.connector</code> module as follows:

from connectors.core.connector import ConnectorError

Add connector operation to a playbook

Once you have completed configuring and deploying your connector, you can add a connector operation to a playbook, by adding the connector as a step in the playbook, as shown in the following image:



You can install different versions of a connector, and while adding a connector operation, you specify a specific version of a connector within a Playbook. In case you have installed multiple connectors, and if the version of the connector specified in the playbook is not found, then the playbook by default uses the latest version. FortiSOAR checks for the latest version of the connector in the format "major version.minor version.patch version". For example, version 2.0.2 is a later version than 1.2.0.

The execute function of connector.py is called when an operation on the connector is invoked. This function takes the dictionary containing the config, operation and params fields. For example:

```
{'config': {'password': password, 'server_url': 'https://xyz.com', 'user': 'admin'},
'params': {'input1': 'value1', 'input2': 'value2'},
'operation': 'function_template'}
```

The return from the <code>execute</code> function is set in the <code>results.data</code> variable of the playbook step. A sample <code>execute</code> function is present in the <code>connector.py</code> section.

The info.json contains output_schema, which defines the keys that are present in the output json on the execution of an operation. The info.json contains some common keys. However, the output json can have additional keys based on the input parameters. You can use these json keys to set the input for subsequent Playbook Steps, using Dynamic Values. For more information, see the *Dynamic Values* section in the "Playbooks Guide."

Configuring a connector to return a response

If you want to return a response from any action of a connector, then you can import the Result class from the connectors framework to your connector.py, and then you can set message attributes such as status, message, etc.

Following is the python snippet for the same:

from connectors.core.connector import Result def action(input, *args, **kwargs): # Do some operation response = api Call(input()) # prepare result result = Result() result.set_status('Successful') result.set_message('Any message you want to return')

Updating a connector configuration using the update_connnector_ config() function

The update connector config () function can be internally called from any connector to update the configuration of any connector by providing the name and version of that connector. Steps to be followed for updating a connector configuration:

1. Import the update connnector config() function from /opt/cyopsintegrations/integrations/connectors/core/utils.py.

result.set data(response)

return result

```
2. Call the update connector config function with the following parameters: < connector name>,
   <connector version>, <update config>, and <config id>.
   update connnector config(<connector name>,<connector version>,<update
   config>,<config id>)
   For example, update connnector config("imap", "3.2.0",
   {"username": "csdamin", "password": "csadminpwd"}, "5785130913212321")
```

Notes:

If you do not provide the <config id>, then the connector configuration that you have marked as default configuration will be updated.

If you have not marked any connector configuration as the default configuration, and you have also not provided the <config id>, then the following error is raised: No configuration found to update. Please add a config id or mark a configuration as the default. in the /var/log/cyops/cyopsintegrations/connectors.log. To resolve this error, either mark a connector configuration as the default configuration or provide the <config id>.

Configuring a custom connector to support data ingestion

If your custom connector also supports data ingestion, you must make the following updates so that your connector works with the ingestion wizard in the FortiSOAR:

- 1. Update the info. ison file as follows:
 - a. "ingestion_supported": true This is a required parameter; if not included, the "Data Ingestion" button will not be displayed in the connector configuration.
 - **b.** Specify the ingestion mode(s) to be used by your custom connector:

```
"ingestion modes": ["scheduled", "notification", "app push"]
```

This is a required parameter, and the value of "ingestion_modes" must be a list containing one or more of the following three elements:

- i. "scheduled": Specify this value if you want to setup ingestion on a schedule. The "Scheduling" page gets displayed in the Data Ingestion Wizard only if you add "scheduled" in "ingestion modes".
- **ii.** "notification": Specify this value if the connector supports a listener for real-time ingestion. The 'Exchange' connector is an example of a connector that supports a listener.
- iii. "app_push": Specify this value if the connector's ingestion is based solely on a push from the integrating application. The 'Splunk Add-on' is an example of an app_push integration.
- c. Specify additional preferences for your custom connector using the "ingestion_preferences" parameter: For example, in the Data Ingestion Wizard, to limit the module selection to specific modules only instead of all modules present on the instance, specify the list of supported modules explicitly using the "modules" key: "ingestion_preferences": {"modules": ["threat_intel_feeds", "indicators"] Or, to give a custom name to the launch button ("Configure Data Ingestion") used to open the 'Data Ingestion Wizard', use the "launch name" key.

For example:

```
"ingestion preferences": {"launch name": "My Custom Label"}
```


2. Update the playbooks.

The data ingestion process is essentially the running of a FortiSOAR playbook. The ingestion flow is comprised of two phases termed as "Fetch" and "Create". You can refer to the sample collection of ingestion-enabled connectors, such as FortiAnalyzer and FortiSIEM, which are included with FortiSOAR.

All playbooks that contribute to the flow must adhere to the following conventions:


- a. They must be added as a part of the 'Sample Collection' shipped with the connector.
- b. All playbooks contributing to ingestion must contain the following tags:

```
<connector name>, dataingestion
```




For example, the MalSilo connector in the following image contains the tag malsilo and dataingestion:

- c. Fetch Playbook: This playbook pulls data from the ingestion source.
 - i. Must have an additional tag named "fetch"
 - ii. The connector action step responsible for fetching the data must be named "Fetch". The data ingestion wizard looks for a step with this name and displays its inputs as 'inputs' on the "Fetch Data" page of the Data Ingestion Wizard:




iii. If the inputs onthe "Fetch Data" page of the Data Ingestion Wizard are different from the inputs on the connector configuration step, then you need to add a "variable" called "_configuration_schema" to the "Start" step and define the "Fetch Data" inputs in the JSON format. The format of the JSON is the same as that for a connector action input. This variable, if present, is given preference over the 'Fetch'




step. An example of the "_configuration_schema" variable with JSON values:

iv. Must have a Set Variable step named "Configuration" as the second step of the playbook. All inputs provided by users in the "Fetch Data" step are saved in this playbook step.




v. The playbook must return data in a variable named "data" as the last step of the playbook.

 ${\{ \text{vars.steps.} < \text{step_name} > .data \} \} }$ of this playbook is what is presented in the "Field Mapping" screen of the Data Ingestion Wizard, and it is also used for record creation during the scheduled runs.




- **d. Create Playbook**: This playbook creates FortiSOAR records for every data element fetched from the data source.
 - i. Must have an additional tag named "create".
 - ii. Must have a "Create Record" step named "Create". The Data Ingestion wizard displays all the data mapping rules using this step. Any changes to the mapping done by the user are also saved back to this step in the playbook.
- e. Ingest Playbook: This is a parent playbook that combines both the "Fetch" and "Create" phases.
 - i. Must have an additional tag named "create".
 - ii. Must invoke the "fetch" and "create" playbooks as "Reference Playbook" steps. The data returned from the "fetch" step must be passed as input to the "create" step.
 - iii. For schedule-based ingestions, you can set the last successful pull time as the last step of this playbook, marking the successful completion of one cycle of ingestion. This ensures that subsequent runs pulls data created or modified after this time. This value can be stored as a FortiSOAR Global Variable. To make a global variable unique per configuration of the ingestion, you can append the config_id to the variable by using the following Jinja expression:

```
<Source>_ {{vars['audit_info']['cyops_playbook_iri'].split('/')[-1].replace ('-',' ')}}
```




You can refer to any data ingestion collection, for example, the "Sample-MalSilo" data ingestion to see




how to save global variables and use them while fetching data.

- 3. Updates specific to Threat Intelligence Management (TIM) ingestion:
 - a. The TIM ingestion integrations must have an additional tag, "ThreatIntel" in the connector's info.json. This tag is used to display the connector in the listing for TIM-enabled connectors: https:
 https:
 content-hub/all-content/?tag=ThreatIntel



- **b.** Instead of the "Create Record" step, the playbooks must use the "Ingest Bulk Feed" step to handle larger volumes of feeds.
- c. Leverage pagination in APIs, as much as possible, while fetching data from the data source. Fetch and create one batch of data before fetching the next page. This reduces the memory requirements for data ingestion. If pagination is not supported by the data source, you can save on memory requirements by invoking the creation playbooks directly from the connector action that fetches data. To do so, take the IRI of the playbook that creates the feed records as an input to the "Fetch and Create" step. Note that the name of this step must also be kept the same.



Use the following function call in the connector to trigger these playbooks:

Import:

```
try:
    from integrations.crudhub import trigger_ingest_playbook
except:
    # ignore. lower FSR version
    # pass
Function Call:
trigger_ingest_playbook(batch, create_pb_id, parent_env=parent_env, batch_
```

Q&A Time

Q1. Why do I need three playbooks - Fetch/Create/Ingest and not just one?

Answer:

The data ingestion collections get invoked from two flows:


size=1000, dedup field="pattern")

- 1. For data mapping using the Data Ingestion Wizard.
- 2. For record creation through schedules or listener based notifications.

 For 1), the wizard invokes the playbook tagged with a "fetch" tag; hence, this playbook must only fetch data, and not create the corresponding records in FortiSOAR, as the user is still evaluating the queries and mappings.

For 2), the complete ingestion flow must run and save the last pulled time values; hence, in this case, the playbook with the "ingest" tag gets called.

However, you could still use a single playbook for the entire data ingestion and put all three tags, "create", "fetch", "ingest". When a playbook is triggered from the data ingestion wizard, it has a variable called "env_setup" in the request object. When the value of the "env_setup" request object is set to 'true', it is used to skip the data creation steps.



Q2. What happens to my configured ingestions when I upgrade the connector?

a. Will the ingestion use the latest connector version?

<u>Answer</u>: Yes. If the new version of the connector is compatible with the previously installed connector version, it is replaced automatically, and the ingestion starts using the latest installed connector version.

b. Are my previous mappings lost since the sample collection is now updated?

<u>Answer</u>: No. When you set up the data ingestion for an integration, it creates a clone of the sample collection. All user inputs from the "Fetch Data" and "Field Mapping" pages of the wizard are stored in the cloned collection. The

cloned collection is the one that is scheduled for ingestion, and not the original sample collection.

c. Will any fixes/changes to the data ingestion be inherited by my existing ingestion configuration?

Answer: Yes, if the changes are in the connector actions.


No, if the changes are in the ingestion playbooks. You can re-configure the ingestion using the new default playbooks in the 'Sample Collection', or manually apply the changes to your cloned playbooks.

Q3. How can I use a custom collection other than the default sample collection?

Answer:

You can build your ingestion collection separately using the steps listed in the Configuring a custom connector to support data ingestion topic, and add the following two **tags** to the **playbook collection**:

- 1. "dataingestion"
- 2. "<connectorname>". For example, "malsilo"



These custom collections are then available as alternates for setting up ingestion in the Data Ingestion Wizard. You can use this feature while building the default ingestion collection for an integration or ship it as a new Solution Pack with customized ingestion.



Building your own Pluggable Enrichment Playbook

The SOAR Framework Solution Pack (SP) version 2.0.0 introduces the 'Pluggable Enrichment' framework, using which you easily design pluggable enrichment playbooks for any integration and use them in the enrichment process without modifying the existing playbooks in '03-Enrich' collection. For detailed information about the SOAR Framework SP, see the SOAR Framework SP documentation in the Content Hub portal. Some threat intelligence connectors already contain pluggable enrichment playbooks; more information of which is available here.

The following steps describe how to design your pluggable enrichment playbooks for 'IP Enrichment' using the 'API Void' integration:

- 1. Install and configure the API Void v1.0.1 connector.
- 2. Navigate to Automation > Playbooks, and search for API Void.
- 3. Select the 'Sample APIVoid 1.0.1' playbook collection.
- 4. Click Add Playbook to create a new pluggable enrichment playbook.
- 5. Specify the name of the new playbook, such as, "IP Address > API Void > Enrichment".
- 6. Choose **Referenced** as the 'Trigger' step, and click **Save** to save the playbook.
- 7. Add appropriate tags to your pluggable enrichment playbook. Since this example is for designing this pluggable enrichment playbook for 'IP Address', add the "IP_Enrichment" tag to the playbook.

You can add the following tags to the pluggable enrichment playbook for different types of indicators:

- Domain: Domain Enrichment
- Email Address: Email Enrichment
- File: File Enrichment
- FileHash-MD5, FileHash-SHA1, FileHash-SHA256: FileHash Enrichment
- IP Address: IP Enrichment
- URL: URL Enrichment
- User: User Enrichment
- **8.** The "Enrich Indicators (Type All)" parent playbook that is part of the "03 Enrich" playbook collection calls the "IP Address > API Void > Enrichment" child pluggable enrichment playbook by passing the following parameters:
 - a. "indicator value": Value of the IP address that needs to be enriched.
 - **b.** "style_colors": Value of default enrichment colors assigned to the indicator based on its reputation. For further details, see the Extending Default Indicator Enrichment Process topic.
- 9. Open the "IP Address > API Void > Enrichment" playbook in the playbook designer, and click **Tools** > **Edit Parameters**.

In the Parameters popup, add the indicator value and style colors parameters.

- **10.** Edit the "IP Address > API Void > Enrichment" playbook as follows:
 - a. Add the **Set Variable** step" with the name as "Configuration", and specify the following variables and their values:
 - useMockOutput: { {globalVars.Demo_mode} }
 To execute the playbook using mock output, set the global variable Demo_mode to true.
 - indicator_value: {{vars.input.params['indicator_value']}}
 The value of the indicator that you want to enrich. This value comes from the parent playbook.
 - good_score: 0 suspicious_score: 89-1 malicious score: 100-90

After enrichment, the API returns a high-reliability value called "verdict," which is used to predict the reputation of indicators.


"good_score" is the range of good verdicts.

"suspicious_score" is the range of suspicious verdicts.

"malicious_score" is the range of malicious verdicts.

You can update the values of these parameters based on your requirements.

- **b.** Add the **Connector** step, and search for the APIVoid v1.0.1 connector. Specify the following values for this step:
 - i. In the $\mbox{\bf Step Name}$ field, specify $\mbox{\bf Get}$ IP Reputation.
 - ii. From the Action drop-down list, select Get IP Reputation.
 - iii. In the IP Address field, specify { {vars.indicator value} }.
- **c.** Add the **Decision** step for checking whether or not the reputation is found:
 - i. In the Step Name field, specify Is Reputation Found.
 - ii. Click Add Condition:
 - i. Define 'Condition 1' as follows:
 (vars.steps.Get IP Reputation.status == "Success" or vars.useMockOutput)
 - ii. From the Select A Step To Execute drop-down list, select Compute API Void Summary.
 - iii. In the Branch Tooltip field, specify Yes.
 - iii. Click Add Default Condition to define the default step as follows:
 - i. From the **Select A Step To Execute** drop-down list, select **No Operation**.
 - ii. In the Branch Tooltip field, specify No.



- d. Add the Utilities step and edit it as follows:
 - i. In the Step Name field, specify Compute API Void Summary.
 - ii. From the Action drop-down list, select Utils: Format as RichText (Markdown).
 - iii. In the Inputs field, specify the code that you want to render as the 'Enrichment Summary' in the Description field of the indicator. You can refer to samples of the code from any pluggable enrichment playbook, for example, pluggable enrichment playbooks in the API Void sample playbook collection, "IP Address > API Void > Enrichment".
- e. Add another Utilities step and edit it as follows:
 - i. In the Step Name field, specify No operation.
 - ii. From the Action drop-down list, select Utils: No Operation.
- f. Add the **Set Variable** step" with the name "Return Output Data", and set the return values to the parent playbook, 'Enrich Indicators (Type All)', present in the '03 Enrich' playbook collection. See the apivoid connector document for the return values that can be sent to the parent playbook.

Sample "IP Address > API Void > Enrichment" pluggable enrichment playbook:



FortiSOAR Connector SDK

The FortiSOAR Connector SDK consists of a simulator for writing and testing your connector. You can use this CLI to help you develop your custom connector, without having a ForiSOAR™ instance.

For information on how to set up and use the FortiSOAR Connector SDK, see Fortinet Developer Network (FNDN). You can also download the Connector SDK from FNDN and use it to develop a custom connector. You must log into FNDN to access the Connector SDK.

Data Ingestion

FortiSOAR has a dedicated data ingestion wizard that facilitates data ingestion from external SIEM solutions and other third-party sources like threat intelligence platforms, email solutions, etc. The wizard also takes care of scheduling data ingestion into FortiSOAR, if the connector is enabled for scheduling.

The Data Ingestion wizard eases data ingestion configuration and mapping of fields between the two systems. The wizard assists in fetching sample data from the source, mapping fields from the source data into a FortiSOAR module, and setting up an ingestion schedule if required and if the connector is enabled for scheduling. Based on the inputs provided in the wizard, the system dynamically generates the ingestion workflows without the user being exposed to the details of playbooks and easing the process of configuring ingestion.

The Data Ingestion wizard allows the mapping of drop-down (picklist) fields and items such that you can map picklist items to a range of values, lesser than, and greater than values. The Data Ingestion wizard allows you to define the frequency at which you want to pull content into FortiSOAR from third-party integration, such as SIEMs that allow you to define the polling frequency. By default, the frequency of pulling content is set at five minutes.

FortiSOAR and its connectors come with sample playbooks for ingesting data from various SIEM sources, Threat Intelligence Platforms, Vulnerability Management Tools, Configuration Management Databases, etc. Connectors that you can use to ingest data through this wizard are enabled by default in FortiSOAR.



Data ingestion is generally mapped to the alerts or incident modules, and from release 7.2.0 onwards, the Incident Response modules get added once you have installed the SOAR Framework Solution Pack (SP). Therefore, for data ingestion to work correctly you must install this solution pack. From release 7.2.0 onwards, the SOAR Framework Solution Pack is installed by default with the fresh installations of FortiSOAR. For detailed information about the SOAR Framework SP, see the SOAR Framework SP documentation.

Data ingestion also has the following features:

- Supports fetching of data for each configuration of your connector, i.e., if you have two configurations present in your connector, then you can pull ingestion data for each configuration.
- Supports multiple queries for pulling data based on your requirement; however, you must specify one query to schedule the pulling of data from the connector into FortiSOAR.
- Supports easy and efficient ingestion of data from various sources using the intuitive UI of the Data ingestion wizard.
- Supports monitoring of the data ingestion that you have set up and provides information on which connectors are
 configured for using the Data Ingestion Wizard on the Data Ingestion tab of the Connectors page. The Data
 Ingestion also provides you other information such as what is the status of a configuration, what is the schedule for
 ingestion, when data was last pulled using that configuration, etc.
- Supports inserting or upserting records in bulk during data ingestion, which improves the performance since all the records are created or upserted in one request.

Modes of Data Ingestion

Data Ingestion can work in any of the following three modes:

- **Notification Based**: Some connectors such as IMAP, Exchange, Syslog, etc have a Notification Service that gets instantly notified when a message arrives on the server. The notification service, in turn, triggers a FortiSOAR playbook to create FortiSOAR records from the fetched data.
- Schedule Based: Some connectors such as QRadar, Anomali, ServiceNow, etc use the Fetch APIs of the
 integration, i.e., for example, the fetch API of Anomali, along with a user-defined query to fetch data from the
 product into FortiSOAR. These fetch playbooks are scheduled to run by default, every 5 mins, or can also be
 scheduled to run according to a user-defined interval.
 - Note that most integrations that support a Notification Based ingestion also support a Schedule Based ingestion. You must, however, configure only one of the two since otherwise both would pull the data from the same source and there might be data loss due to conflicts.
- App Push: Some connectors such as Splunk have an add-on that is provided by FortiSOAR and which can be
 installed on the server-side to push data from the integration to FortiSOAR. The add-on is configured with a userpassword or appliance-based authentication in FortiSOAR and it triggers FortiSOAR playbooks to create the
 records in FortiSOAR.


Permissions required for using the Data Ingestion Wizard

For permissions on using connectors, see the Introduction to connectors chapter. Apart from this, to use data ingestion, you must be assigned a role that has Read and Update permissions on the Connectors module and Create, Read, Update, and Execute permissions on the Playbooks module. If you want to schedule the data ingestion, then you are also required to have Create, Update and Read permissions on the Schedules module.


Data Ingestion Wizard

The **Data Ingestion** page displays connectors that are configured for using the Data Ingestion Wizard, i.e., you can use the data ingestion wizard to ingest data into FortiSOAR for these connectors.

To view the data ingestion page, log on to FortiSOAR, and on the left navigation pane, click **Automation > Data Ingestion**, which displays all the connectors that are installed on your system and are enabled for data ingestion, along with the number of configurations available for that connector.



From version 7.0.2 onward, you can set the logging levels (INFO or DEBUG) for your ingestion playbook by clicking **Set Playbook Logging Levels**, which displays the Playbook Execution Log Level dialog:



From the **Select Execution Log Level** field, select the logging level that you want to set for this playbook and click **Apply**. By default, the INFO log level is set for ingestion playbooks; however, if you want extensive logging for ingestion playbooks, then retain the logging level as DEBUG, and click **Apply**.



Changes made to the logging level apply to all ingestion playbooks across all the configurations of the particular connector. If you want to update only a particular configuration of the connector, then you have to go to the respective playbook collection and selectively update the logging levels.

You can also run the data ingestion wizard on agent configurations. To display the details of the configurations, click the <number of configurations> configurations available link. To view the configuration details of the current node, click **Self**. To view the agent configuration details, click **Agent**, and then from the drop-down list, select the name of the agent whose configuration details you want to view, as shown in the following image:



Details that are displayed for the configurations are as follows:


- Status of a configuration, whether it is Available or Disconnected.
- **Schedule** for running the ingestion, i.e., what is the frequency at which the third-party integration will be polled to ingest data into FortiSOAR.
- Last Data Pulled on contains the DateTime when the data was last pulled into FortiSOAR using this configuration.
- Actions contain the following options:
 - **Configure Ingestion**: Clicking this link displays the Data Ingestion Wizard. This option is displayed when you are configuring data ingestion for the first time for a particular configuration.
 - Ingestion Settings: Clicking this link displays the Data Ingestion Wizard with the configured ingestion settings. This

option is displayed when you have already configured data ingestion for a particular configuration.

Ingestion Playbooks: Clicking this link opens the ingestion playbooks collection in a new window.

Trigger Ingestion Now: Clicking this link immediately starts the data ingestion process. Subsequent data ingestion occurs based on the data ingestion schedule you have set.

Start Ingestion / Stop Ingestion: Clicking this link either starts ingestion for a newly-added configuration or stops ingestion for a particular configuration based on the ingestion settings you have configured.






If you have upgraded to FortiSOAR 6.0.0 or later from an earlier version, then before you reconfigure ingestion for the same connector configuration, you must deactivate the earlier ingestion playbooks that are present in the ingestion collection for the connector. The links to the ingestion playbooks that were created prior to the upgrade will be present on the **System Fixtures** page in the "Ingestion Playbooks" section will not be visible in the Data Ingestion tab (new in version 6.0.0) of the "Connectors" page. If your data ingestion is schedule-based, then you must also stop or delete the earlier schedules for the connector.

Process of ingesting data using the Data Ingestion Wizard

- 1. Log on to FortiSOAR.
- On the left navigation pane, click Data Ingestion (see Data Ingestion) or go to Content Hub or Automation >
 Connectors and click the Manage tab, which lists the installed connectors in the card view. For more information, see Data Ingestion.
- **3.** On the **Manage** tab, click the connector card using which you want to ingest data. For our example, we have chosen IBM QRadar.
- **4.** On the Connector Configuration popup, from the **Select Configuration** drop-down list select the configuration for which you want to configure the ingestion, and then click **Configure Data Ingestion**.



Only connectors that have been enabled for data ingestion will have the **Configure Data Ingestion** button. **Note**: To ingest data, your connector must be in the **Available** state.

5. Click Configure Data Ingestion to display the Start screen of the Data Ingestion Wizard.




If you are running data ingestion for the first time, click the Let's Start by fetching some data button to display the

Fetch Sample Data screen. However, if you have previously run ingestion using the IBM QRadar connector, you will also see the Let's start with last saved data button. Release 7.2.0 has enhanced data ingestion to save the pulled results from the previously run ingestion and use the same instead of re-fetching the results. Clicking Let's start with last saved data moves directly to the Field Mapping screen, skipping the Fetch Sample Data screen, as the data pulled from the previous run ingestion will be used. In this case, a Skip button is also added to the Fetch Data screen.


Release 7.2.0 also provides you with the option of selecting a custom playbook collection, other than the sample playbook collection that is bundled with the connector, to be used for ingesting data. Examples for the need of custom playbook collections could be in the case of a War Room that is set up with the unified communication feature, where we need communication to link with the war room record whenever a relevant email is ingested, which can be achieved by a custom data ingestion playbooks collection, or in case of MSSP environments where custom data mapping can be referenced for onboarding new customers, etc. Therefore, from release 7.2.0 onwards, you can click **Advance Settings** and from the **Choose custom integration collection** drop-down list, you can select playbooks from different collections that support data ingestion to be used for data ingestion or upload a custom data ingestion playbook collection. For playbook collections to be listed in the **Choose custom integration collection** drop-down list, ensure that playbook collection has a #dataingestion tag and the ingestion playbooks have the #<nameOfConnector> and #dataingestion tags, for example, #qradar #dataingestion. If you select a custom data ingestion playbook collection, then data is fetched using the selected playbook collection.

Note: When you use a custom playbook collection for data ingestion, then in this case the sample playbook collection gets overridden by the custom playbook collection in the ingestion collection, i.e., in the playbooks collection that is shown when you click Playbooks in the connector row on the Data Ingestion page.

6. Sample data is required to create a field mapping between your connector data and FortiSOAR. The sample data is pulled from connector actions or ingestion playbooks. By default, FortiSOAR ingests data using an "Ingestion Playbook" that is included by default with each connector that is enabled for data ingestion.
A connector would generally require some configuration details, which you will require to fill in on this screen. For example, in the case of IBM QRadar, in the Search Query field, enter the query based on which you want to fetch data into FortiSOAR. In the Pull Offenses in Last X Min, enter the number of minutes for which you want to retrieve created or modified offenses from IBM QRadar, for example, 10, in this case, the data ingestion wizard will fetch offenses that are created or modified in the last 10 minutes from IBM QRadar. In the Timezone of the QRadar server, specify the timezone of the QRadar server; this is used to convert for pulling offenses in the last X minutes, and in the Event Record Limit, specify the maximum offenses records you want to fetch, and then click Fetch Data.




Another example is **Syslog** where you will see the **Message_samples** field in which you can add samples of messages in the CEF Format using which you want to map the fields:



- 7. On the Field Mapping screen, map the fields of the sample data to the fields present in FortiSOAR as follows:
 - a. The Field Mapping screen displays the Sample Data on the right side of the screen and the Field Mapping (FortiSOAR fields) on the left side of the screen. The sample data is in the form of a Key-Value pair. From the Module drop-down list that appears next to Field Mapping, select the FortiSOAR module for which you want to map the fields. The default module will be already be selected, for example, Alerts.
 Note: If you select any module other than the default module, you will require to remap all the fields.

b. From the Sample Data fields, map the fields onto the fields present in the Alerts module as follows: Important: Some fields such as Name and some picklists can come pre-mapped with their keys. You do not require to re-map these fields unless you want to override their default values. You can search for fields in the record and the sample data.


To map a field, click the key in the sample data to add jinja for the field. For example, to map the destination_networks field from the IBM QRadar sample data to the Destination IP field in FortiSOAR, click **Destination IP** and then click **destination_networks**:



To view the key of a field, double click in the field, for example, if you click the newly-mapped description field, its key { {vars.sourcedata["destination_networks"] } } will be displayed. Once the key (which is in jinja) is displayed, this field will always be displayed with the key value.

Note: If bulk insert or upsert is supported for the connector, then the key value changes from {{vars.sourcedata["name of the field"]}} to {{vars.item["name of the field"]}}. For example, {{vars.item["destination networks"]}}.


From version 7.0.0 onwards, if your administrator has enabled any 'Lookup' or 'Picklist' type of field to accept the values generated from the recommendation engine, then you will see an **Auto populate** checkbox appearing beside this field. For example, the 'Type' field in the following image:



If you select the **Auto populate** checkbox, and users have not specified any values for such fields, then the value of such fields gets auto-populated with the values from the recommendation engine that is based on learning from past similar records.

Picklists can come pre-populated with their defined defaults if they are available. You can also map picklists using the wizard.

To map a picklist, such as **Status**, select the picklist whose value you want to map. For example, severity from the IBM QRadar sample data can be mapped to the Severity picklist in FortiSOAR by clicking severity. FortiSOAR would already have mapped this picklist by default, and it will appear as severity whose key value is { {vars.sourcedata["severity"] } }. Next, you must map the items of the Reputation picklists. To view and map the items of the Severity picklist in FortiSOAR, click the down arrow (v). The Severity picklist has items such as Minimal, Low, Medium, Hight, and Critical. These picklist items can be mapped as per the values defined in the source. You can map more than one picklist item in FortiSOAR can map to a single value in the source. For example, you can map both 2 to both Minimal and Low in FortiSOAR. You can also map one picklist item in FortiSOAR to two values or more values in the source, for example, Low can be 2,3,4. In this case, if the severity field in IBM QRadar has values 2, 3, or 4, then all cases with confidence 2 to 4 will be mapped to **Low** severity in FortiSOAR. You can also specify the mapping of a range of values, lesser than, and greater than values. For example, **High** can be mapped 7..10 in FortiSOAR, which means that if the severity field in IBM QRadar contains any value between 7 to 10 they will be mapped as High severity in FortiSOAR. Similarly, if you map Critical to >10<20 in FortiSOAR this means that if the severity field in IBM ThreatStream contains any value greater than 10 and less than 20, then they will be mapped to Critical severity in FortiSOAR.



Note: Multiple expressions of type "number" must be separated by a space. Also, in the case of a range, there must be two dots between the numbers.

You can also specify string values in a picklist such as Open, In Progress, Closed, etc. Multiple expressions of type "string" must be comma-separated.


In case you want to use another query to fetch additional data to create a comprehensive mapping, click the + Fetch additional sample data link that appears in the Sample Data header. Clicking the + Fetch additional sample data link opens the Configurations dialog in which you can change the configuration such as, updating the Search_query, and then click Fetch Data. The data ingestion wizard fetches the data based on the updated configuration on a new page in the Sample Data section. You can continue mapping based on the newly fetched data.

Once you are satisfied with the mappings, click Save Mapping & Continue.


8. (Optional) If your connector is enabled for scheduling, such as IBM QRadar, then you will be shown the Scheduling screen, using which you can specify the schedule for data ingestion from the connector into FortiSOAR, i.e., you can specify the frequency of polling a third-party integration, such as SIEM, so that the content gets pulled from the third-party integration into FortiSOAR. By default, scheduling is set to pull data every 5 minutes.

To configure scheduling, from the Do you want to schedule the ingestion? drop-down list, select Yes.

In the Configure Schedule Settings section, specify the Cron expression for the schedule. For example, if you want to pull data from IBM QRadar every 15 minutes, click Every X Minute and in the minute box enter */15.



Note: If you select the Limit execution to one active instance at a time checkbox, then do not rerun the workflow (schedule) if the previous schedule is still running. Some connectors such as IMAP support data ingestion using both a scheduled-based pull as well as instant notification using the Notification Service. You must, however, configure only one of the two, since both would otherwise pull the data from the same source and there could be data loss due to conflicts. Therefore, the <code>Scheduling</code> screen for the IMAP connector displays the following warning:



Only if you want to ingest data using a scheduled-based pull, then you should use the Scheduling screen to specify the schedule for data ingestion from the IMAP connector into FortiSOAR.

Once you are satisfied with the scheduling, click **Save Settings & Continue**.

9. The **Summary** screen displays a summary of the mapping done, and it also contains links to the Ingestion playbooks.



Click **Trigger Ingestion Now** to immediately begin the process of data ingestion. Subsequent data ingestion occurs based on the data ingestion schedule you have set.

Click **Done** to complete the data ingestion and exit the Data Ingestion Wizard.

Notes for Data Ingestion Playbooks:

- The Summary step contains links to playbooks that contain the data mapping based on the mappings you have specified in the wizard. You can click the links and open the playbook in the Playbook Designer.
 For example, to open the playbook that fetches data from the Anomali ThreatStream connector, click Anomali ThreatStream > Ingest link, which opens the Anomali ThreatStream > Ingest playbook in the Playbook Designer.
- You can open the Data Ingestion Playbooks collection by clicking here in the Summary step.
- You can modify these data ingestion playbooks or the mappings in the playbooks using the Playbook Designer and those modifications are reflected in the mappings, i.e., if you open the "Data Ingestion Wizard" again you will see the modified content.

Notes for Data Ingestion

- If you are using the IMAP connector for data ingestion, then you must ensure that you configure either a scheduled-based pull, using Scheduling in the Data Ingestion Wizard, or the instant notification method using the Email Notification Service, by clicking the Enable Email Notification Service in the IMAP connector configuration pane. If you configure both then both the methods would pull the data from the same source and there could be data loss due to conflicts.
- If you are using the IMAP connector for data ingestion and at the field mapping stage you change the default module
 for data ingestion, which is set as **Alerts** to any other module, for example, **Emails**, then the playbook used for
 ingesting data remain active and no records will be created. To get the data ingestion to work correctly, do the
 following:

Open the > IMAP > Create Record playbook and click the **Upsert File Indicators** step. In the **Upsert File** Indicators step, you need to initialize the IRI value of the module that you want to use for data ingestion instead of

the alert record IRI. To achieve this, click the **emailRecordIRI** field, and use "Dynamic Values" to enter the IRI value of the required module or enter the following Jinja value: $\{\{vars.steps.Create_Record['@id']\}\}$. For example, if you have changed the module used for data ingestion from Alerts to Emails, then to initialize the emailRecordIRI variable instead of alertRecordIRI, in the **emailRecordIRI** field, enter the $\{\{vars.steps.Create_Record['@id']\}\}$ value.

Also, note that If you select any module other than the default module, you will require to remap all the fields.

- If you are using the Syslog connector for data ingestion, then you must ensure playbooks used for data ingestion provide input in the CEF format, otherwise, you require to modify the playbooks. Since CEF is the most common format for Syslog messages, the default data ingestion playbooks parse the message as CEF. If the Syslog messages from your server are non-CEF complaint, you can modify the "Parse CEF" step in the > Syslog> Fetch playbook that is part of the playbooks shipped with the Syslog connector, before you configure Data Ingestion. The Syslog connector also provides "Parse Message" action to parse RFC 3164 and RFC 5424 formatted messages and convert these message formats to CEF format, instead of using the "Parse CEF" step.
- From version 7.0.2 onwards the ingestion wizard has been enhanced to not fail if there are no #fetch or #create playbooks. There can be connectors that require only the #ingest playbook that contains a single action, which pulls data and creates records. Such connectors do not require the #fetch playbook since data is not required for custom module mapping and the #create playbook is not required since the 'Create Record' step is not needed. Therefore, in this case, the Data Ingestion Wizard works as follows:
 - The Data Ingestion Wizard is loaded even if only the 'Ingest' playbook is present; and in this case, the wizard displays only the Scheduling screen.
 - If the 'Fetch' playbook is not present, the wizard does not display the Fetch Data screen.
 - If the 'Create' playbook is not present or the 'Create Record' step is not present, the wizard does not display the Field Mapping screen.

Troubleshooting


The Fetch Data screen in case of IMAP displays the ERROR :: create failed: [ALREADYEXISTS] Folder name ... error

This error occurs when you are running the Data Ingestion Wizard using the IMAP connector. Click Fetch Data on the Fetch Data screen and an error such as "> IMAP > Fetch has failed because CS_INTEGRATION-5: Error occurred while executing the connector action ERROR:: create failed [ALREADYEXISTS] Folder name conflicts with existing folder name....." is displayed.

The above error can occur due to the following reasons:

- This issue occurs if the **Email destination** folder specified on the server is similar to an existing folder. Mailbox names are case sensitive on the creation of folders using the IMAP client, for example, if you specify MyFolder in the **Email destination** field and a folder named myfolder already exists on the server, then this error will be displayed on the Fetch Data screen when you are running the Data Ingestion Wizard.
- This error also occurs if the folder that you have specified does not have permission for the IMAP client.

Resolution



In the IMAP configuration pane, update the folder name in the Email destination field and save the configuration:

Ensure that you provide appropriate permissions to the email destination folder for the IMAP client.

Post upgrade to FortiSOAR 6.0.0 or later from version 5.1.0 does not save any data ingestion configurations

If you have upgraded your FortiSOAR version from 5.1.0 to 6.0.0 or later, you will see data ingestion configurations that you had saved in version 5.1.0 are not available in version 6.0.0. You will not see any schedules, ingestion playbook link, or actions button on the Data Ingestion page. However, your data ingestion will continue to run. This is because support for fetching data for each configuration of your connector has been introduced in version 6.0.0 and therefore, the older data ingestion configurations and playbooks have been deprecated.

Resolution

Rerun the data ingestion wizard, i.e., reconfigure your data ingestion if required. Note that your previously configured data ingestion will continue to run, however, you will not be able to see the historical data. If you do require to reconfigure the data ingestion, then you must ensure that you stop your previous configured data ingestion, otherwise both the current and the old data ingestion will continue to run.



modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.