



FortiManager - Upgrade Guide

Version 6.0.12



FORTINET DOCUMENT LIBRARY

https://docs.fortinet.com

FORTINET VIDEO GUIDE

https://video.fortinet.com

FORTINET BLOG

https://blog.fortinet.com

CUSTOMER SERVICE & SUPPORT

https://support.fortinet.com

FORTINET TRAINING & CERTIFICATION PROGRAM

https://www.fortinet.com/training-certification

FORTINET TRAINING INSTITUTE

https://training.fortinet.com

FORTIGUARD CENTER

https://www.fortiguard.com

END USER LICENSE AGREEMENT

https://www.fortinet.com/doc/legal/EULA.pdf

FEEDBACK

Email: techdoc@fortinet.com



June 8, 2023 FortiManager 6.0.12 Upgrade Guide 02-6012-918299-20230608

TABLE OF CONTENTS

Introduction	4
Preparing to Upgrade FortiManager	5
Upgrading ADOMs	5
Downloading files from Customer Service & Support	6
Downloading release notes and firmware images	6
Downloading MIB files for SNMP	
FortiManager firmware images	
FortiManager VM firmware images	
Build numbers	
Reviewing FortiManager 6.0.12 Release Notes	
Planning when to upgrade	
Installing pending configurations	
Reviewing status of managed devices CLI example of diagnose dvm adom list	
CLI example of diagnose dvm device list	
CLI example of diagnose dvm group list	
Checking FortiManager databases	
When upgrading from 5.6.1 and later	
When upgrading from 5.6.0	14
Reviewing FortiManager System Settings	15
Backing up configuration files and databases	15
Creating a snapshot of VM instances	16
Upgrading FortiManager	17
Upgrading FortiManager Firmware	17
Upgrading the firmware for an operating cluster	18
Checking FortiManager log output	19
Checking FortiManager events	19
Downgrading to previous firmware versions	20
Verifying FortiManager Upgrade Success	21
Checking Alert Message Console and notifications	21
Checking managed devices	21
Previewing changes for a policy package installation	22
Supported Models	23
FortiManager Firmware Upgrade Paths	24
Change Log	27

Introduction

This document describes how to upgrade FortiManager to 6.0.12. This guide is intended to supplement the *FortiManager Release Notes*, and it includes the following sections:

- Preparing to Upgrade FortiManager on page 5
- Upgrading FortiManager on page 17
- Verifying FortiManager Upgrade Success on page 21
- Supported Models on page 23
- FortiManager Firmware Upgrade Paths on page 24



Firmware best practice: Stay current on patch releases for your current major release. Only upgrade to a new major release or version when you are looking for specific functionality in the new major release or version. For more information, see the *FortiManager Release Notes*, or contact Fortinet Customer Service & Support (https://support.fortinet.com/).

Upgrade FortiManager before upgrading FortiOS, and be sure to maintain release version compatibility at all times.

Preparing to Upgrade FortiManager

We recommend performing the following tasks to prepare for a successful upgrade of a FortiManager unit. Following is a summary of the preparation tasks and a link to the details for each task.

To prepare for upgrading FortiManager (summary):

- 1. If necessary, upgrade all ADOMs to version 5.2 or higher. FortiManager 5.6.0 and higher supports ADOM versions 5.2, 5.4, 5.6, or 6.0. See Upgrading ADOMs on page 5.
- 2. Download release notes, firmware images, and SNMP MIB files. See Downloading files from Customer Service & Support on page 6.
- 3. Review release notes. See Reviewing FortiManager 6.0.12 Release Notes on page 8.
- 4. Plan when to perform the upgrade. See Planning when to upgrade on page 8.
- **5.** Install pending configuration files. See Installing pending configurations on page 8.
- 6. Review the status of managed devices. See Reviewing status of managed devices on page 9.
- 7. Check the status of FortiManager databases. See Checking FortiManager databases on page 11.
- 8. Review FortiManager System Settings pane. See Reviewing FortiManager System Settings on page 15.
- 9. Back up configuration files and databases. See Backing up configuration files and databases on page 15.
- 10. Clone VM instances. See Creating a snapshot of VM instances on page 16.

Upgrading ADOMs

If you have ADOMs that are earlier than version 5.2, upgrade these ADOMs to a supported version. Supported ADOM versions are 5.2, 5.4, 5.6, and 6.0.

To upgrade ADOM version:

- 1. In the older version ADOM, upgrade one of the FortiGate units to FortiOS 5.2 or later, and then resynchronize the device.
 - All the ADOM objects, including Policy Packages, remain as 5.0 objects.
- 2. Upgrade the rest of the FortiGate units in the older version ADOMs to FortiOS 5.2 or later.
- **3.** Upgrade the ADOM to version 5.2 or later.
 - a. Ensure that you are logged into FortiManager as a super user administrator.
 - **b.** Go to System Settings > All ADOMs.
 - c. Right-click an ADOM and select *Upgrade*.
 - d. Click OK in the confirmation dialog box to upgrade the ADOM.
 If all the devices in the ADOM are not already upgraded, the upgrade is aborted and an error message is displayed. Upgrade the remaining devices in the ADOM and then upgrade the ADOM again.

All the database objects are converted to the new version's format and the GUI content for the ADOM changes to reflect the new version's features and behavior.

For more information, see the FortiManager Administration Guide.

Downloading files from Customer Service & Support

You can download release notes and firmware images from the Fortinet Customer Service & Support portal at https://support.fortinet.com. If you are using SNMP to monitor equipment, you can also download MIB files from the Fortinet Customer Service & Support portal.

This section contains the following topics:

- Downloading release notes and firmware images on page 6
- Downloading MIB files for SNMP on page 7
- FortiManager firmware images on page 7
- FortiManager VM firmware images on page 7
- Build numbers on page 8

Downloading release notes and firmware images

Firmware images are located on the Fortinet Customer Service & Support portal, and they are organized by firmware version, major release, and patch release.

For information about the naming convention of firmware images and VM firmware images, see FortiManager firmware images on page 7, FortiManager VM firmware images on page 7, and Build numbers on page 8.



We recommend running an MD5 checksum on the firmware image file.

To download release notes and firmware images:

- 1. Log in to the Fortinet Customer Service & Support portal at https://support.fortinet.com.
- 2. Go to Download > Firmware Images.
- 3. In the Select Product dropdown list, select FortiManager.
- 4. Download the release notes for the 6.0.12 build:
 - **a.** On the *Release Notes* tab, click the 6.0.12 Build <number> link. The Document Library is displayed.
 - b. Download the release notes.
- **5.** Download the firmware image:
 - a. Return to the Fortinet Customer Service & Support portal, and click the Download tab.
 - **b.** Go to the *v6.00* > *6.0* > *6.0.12* folder, and locate the firmware image for your device or VM.
 - **c.** Download the firmware image by clicking the *HTTPS* link. An HTTPS connection is used to download the firmware image.
 - d. Click the Checksum link for the image that you downloaded.
 The image file name and checksum code are displayed in the Get Checksum Code dialog box.
 - e. Confirm that the checksum of the downloaded image file matches the checksum provided on the download site.

Downloading MIB files for SNMP



If you are not using SNMP to monitor equipment, you can skip this procedure.

If you are using SNMP to monitor equipment, download the following MIB files from the Fortinet Customer Service & Support portal:

- FORTINET-FORTIMANAGER-FORTIANALYZER-MIB.mib, which is used with both FortiManager and FortiAnalyzer
- · Fortinet Core MIB file, which is used with all Fortinet products

To download SNMP MIB files:

- 1. Log in to the Fortinet Customer Service & Support portal at https://support.fortinet.com.
- 2. Go to Download > Firmware Images.
- 3. In the Select Product dropdown list, select FortiManager.
- **4.** Download the MIB file for the FortiManager 6.0.12 release:
 - **a.** On the *Download* tab, go to the v6.00 > 6.0 > 6.0.12 > MIB folder.
 - **b.** Download the MIB file by clicking the *HTTPS* link. An HTTPS connection is used to download the firmware image.
 - Click the Checksum link for the image that you downloaded.
 The image file name and checksum code are displayed in the Get Checksum Code dialog box.
 - **d.** Confirm that the checksum of the downloaded image file matches the checksum provided on the download site.
- 5. Download the Fortinet Core MIB file:
 - **a.** On the *Download* tab, go to the *v6.00* > *Core MIB* folder.
 - b. Download the MIB file by clicking the HTTPS link.
 An HTTPS connection is used to download the firmware image.
 - c. Click the Checksum link for the image that you downloaded.
 The image file name and checksum code are displayed in the Get Checksum Code dialog box.
 - **d.** Confirm that the checksum of the downloaded image file matches the checksum provided on the download site.

FortiManager firmware images

The firmware images in the folders follow a specific naming convention, and each firmware image is specific to the device model or VM.

For example, the FMG_1000D-v6-build0457-FORTINET.out image found in the /FortiManager/v6.00/6.0/6.0.0/ folder is specific to the FortiManager 1000D device model.

FortiManager VM firmware images

Fortinet provides FortiManager VM firmware images for a number of virtualization environments.

Firmware images follow a specific naming convention, and each firmware image is specific to the VM environment. All firmware images for VM upgrades have filenames that end with .out.

For example, the FMG_VM64_HV-v6-build0457-FORTINET.out image is specific to upgrade for the Hyper-V platform.



For more information, see the FortiManager data sheet at https://www.fortinet.com/products/management/fortimanager.html.

VM installation guides are available in the Fortinet Document Library.

Build numbers

Firmware images are generally documented as build numbers. New models may be released from a branch of the regular firmware release. As such, the build number found in the *System Settings > Dashboard > System Information* widget and the output from the <code>get system status CLI</code> command displays this four-digit build number as the build number.

To confirm that you are running the proper build, the output from the get system status CLI command has a Branch Point field that displays the regular build number.

Ensure that FortiManager 6.0.12 can run on your FortiManager model. See Supported Models on page 23.

Reviewing FortiManager 6.0.12 Release Notes

After you download the release notes for FortiManager 6.0.12, review the special notices, upgrade information, product integration and support, resolved issues, and known issues.

Planning when to upgrade

Plan a maintenance window to complete the firmware upgrade. If possible, you may want to set up a test environment to ensure that the upgrade does not negatively impact your network or managed devices.

Installing pending configurations


Prepare your device for upgrade by installing any pending configurations, and ensure that your managed devices are running the appropriate firmware versions as documented in the firmware Release Notes.

Reviewing status of managed devices

Before starting an upgrade, use the *Device Manager* pane to review the status of all managed devices to ensure they have a status of *In Sync*.

Either correct devices without an In Sync status or make note of them prior to starting the upgrade.

Following is an example of the Device Manager pane:



Also, you can use the following CLI commands to gather detailed properties of managed devices, device groups, or ADOMs. The example output that follows highlights the important properties and attributes.

- diagnose dvm adom listdiagnose dvm device list
- diagnose dvm group list

This section contains the following topics:

- · CLI example of diagnose dvm adom list on page 9
- · CLI example of diagnose dvm device list on page 10
- · CLI example of diagnose dvm group list on page 10

CLI example of diagnose dvm adom list

Following is an example of the CLI output for the diagnose dvm adom list command:

```
# diagnose dvm adom list
There are currently 26 ADOMs:
OID STATE PRODUCT OSVER MR NAME MODE VPN MANAGEMENT IPS
...
239 enabled FOS 5.0 4 54-ADOM Normal Policy & Device VPNs 10.00032 (regular)
141 enabled FOS 5.0 4 54-VPN Normal Central VPN Console 6.00741 (regular)
...
---End ADOM list---
```

The following properties should be the same before and after the upgrade:

- · Total number of ADOMs.
- · Name of each ADOM.
- VPN management mode. There are two VPN management modes: Policy & Device VPNs or Central VPN Console.

CLI example of diagnose dvm device list

Following is an example of the CLI output for the diagnose dvm device list command:

This command shows the total number of devices or VDOMs, the configuration status of devices and policy packages, and the connection status. The number of managed devices or VDOMs should be the same before and after the upgrade.

- If the device configuration or policy package status (db) is modified, we recommend installing the changes before upgrading.
- The policy package status (pkg) shows if there is any pending package change on a policy package that has been linked to a device or VDOM. This status can be modified, never-installed, or unknown.
- The connection status (conn) is either up or down.

CLI example of diagnose dvm group list

Following is an example of the CLI output for the diagnose dvm group list command:

```
FMG-v54 # diagnose dvm group list
There are 2 groups:
OID NAME ADOM
277 FGT_Group1 54-VPN
+DEVICE oid=162 name=FGTVM93
278 FGT_Group2 54-VPN
+DEVICE oid=265 name=FGTVM94
---End group list---
```

The number of groups and their members should be the same before and after the upgrade.

Checking FortiManager databases

Before upgrading, it is recommended that you check the integrity of FortiManager databases using the following CLI commands. If you find any errors, you can fix the errors before the upgrade.

- If you need to fix database errors, back up before making any changes. See Backing up configuration files and databases on page 15.
- · Before running integrity check commands, ensure only one admin is logged in and no objects are locked.
- If workspace mode is enabled, you must unlock all ADOMs before running any integrity commands. For information on workspace mode, see the *FortiManager Administration Guide*.

This section starts with CLI commands that you can use for all versions of FortiManager. However, some of the CLI commands listed later in this section are available only for some versions of FortiManager. The following sections identify CLI commands that are version-dependent:

- When upgrading from 5.6.1 and later on page 13
- When upgrading from 5.6.0 on page 14

diagnose pm2 check-integrity all

Check the integrity of the Policy Manager database by using the following command:

diagnose pm2 check-integrity all.



The diagnose pm2 check-integrity all command only detects errors. It cannot correct errors. If any errors are found, the only option is to restore from the last good backup before upgrading.

Example 1 with error:

```
FMG-VM64 # diagnose pm2 check-integrity all --- pragma integrity_check adom db --- Error: database disk image is malformed pragma integrity_check fails: /var/pm2/adom153 >>> total: 10 failed: 1
```

Example 2 without error:

```
FMG-VM64 # diagnose pm2 check-integrity all
--- pragma integrity_check adom db ---
--- total: 15 ok.
--- pragma integrity_check device db ---
--- total: 1 ok.
--- pragma integrity_check global db ---
--- total: 2 ok.
--- pragma integrity_check ips db ---
--- total: 3 ok.
--- pragma integrity_check task db ---
--- total: 1 ok.
--- pragma integrity_check ncmdb db ---
--- total: 18 ok.
```

diagnose dvm check-integrity

Check the integrity of the Device Manager database by using the following command:

```
diagnose dvm check-integrity.
```

Example 1 with error:

```
FMG-VM64 # diagnose dvm check-integrity
[1/8] Checking object memberships ... correct
[2/8] Checking device nodes ... 0 change(s) will be made (263 error(s))
[3/8] Checking device vdoms ...
...
The above changes will be made to the database, however it is recommended to perform a backup first.
Do you want to continue? (y/n)
```

Example 2 without error:

```
FMG-VM64 # diagnose dvm check-integrity
[1/8] Checking object memberships ... correct
[2/8] Checking device nodes ... correct
[3/8] Checking device vdoms ... correct
[4/8] Checking duplicate device vdoms ... correct
[5/8] Checking device ADOM memberships ... correct
[6/8] Checking groups ... correct
[7/8] Checking group membership ... correct
[8/8] Checking task database ... correct
```

diagnose cdb check adom-integrity

Check the integrity of ADOM configurations in the database by using the following command:

diagnose cdb check adom-integrity.



This command does not work on version 5.4.3 or versions earlier than 5.2.11.

Example 1 with error:

```
FMG-VM64 # diagnose cdb check adom-integrity

General updating - adom FWF_LAB ....100% Ready to update

General updating - adom FWF_Root ....100% Ready to update

General updating - adom root ....100% An error has occured: (errno=33):duplicate

If the update check returns an error, please contact Fortinet Support for assistance.
```

Example 2 without error:

```
FMG-VM64 # diagnose cdb check adom-integrity

General updating - adom FWF_Root ......90%..100% Ready to update

General updating - adom FWF_ADOM_50 ......90%..100% Ready to update

General updating - adom FWF_ADOM_52 ...........90%..100% % Ready to update

General updating - adom root ....100% Ready to update
```

diagnose cdb check policy-packages

Check the integrity of the policy packages by using the following command:

```
diagnose cdb check policy-packages.
```

Example 1 with error:

```
FMG-VM64 # diagnose cdb check policy-packages
Adom VPNConsole
  [1/4] Checking Scope ... correct
  [2/4] Checking Dynamic mappings ... 2 change(s) will be made
  [3/4] Checking Policy package settings ... correct
  [4/4] Checking Undeleted objs ... correct
Adom root
  [1/4] Checking Scope ... correct
  [2/4] Checking Dynamic mappings ... correct
  [3/4] Checking Policy package settings ... correct
  [4/4] Checking Undeleted objs ... correct
  [4/4] Checking Undeleted objs ... correct
The above change(s) will be made to the database, however it is recommended to perform a backup first.
Do you want to continue? (y/n)
```

Example 2 without error:

```
FMG-VM64 # diagnose cdb check policy-packages
Adom FG54

[1/4] Checking Scope ... correct
[2/4] Checking Dynamic mappings ... correct
[3/4] Checking Policy package settings ... correct
[4/4] Checking Undeleted objs ... correct
Adom root

[1/4] Checking Scope ... correct
[2/4] Checking Dynamic mappings ... correct
[3/4] Checking Policy package settings ... correct
[4/4] Checking Undeleted objs ... correct
```

When upgrading from 5.6.1 and later

This section describes the commands that you can use when upgrading to FortiManager 6.0.12 from 5.6.1 and later versions.

diagnose cdb upgrade check +all

Check the integrity of object configuration database, reference table, ADOM database, DVM database, and invalid policy package and template installation targets by using the following command:

```
diag cdb upgrade check +all
```



This command does not work on version 5.6.0 or earlier.

Example

```
FMG-VM64 # diag cdb upgrade check +all
Checking: Object config database integrity
No error found.

Checking: Reference table integrity
No error found.

Checking: Repair invalid object sequence
No error found.

Checking: Reassign duplicated unid in ADOM database
No error found.

Checking: Resync and add any missing vdoms from device database to DVM database
No error found.

Checking: Invalid policy package and template install target
No error found.
```

When upgrading from 5.6.0

This section describes the commands that you can use when upgrading to FortiManager 6.0.12 from 5.6.0.

diagnose cdb check objcfg-integrity

Check the integrity of the object configuration database table by using the following command:

```
diagnose cdb check objcfg-integrity.
```

Example:

```
FMG-VM64 # diagnose cdb check objecg-integrity Checking object config database table columns ... correct
```

diagnose cdb check reference-integrity

Check the integrity of the ADOM reference table by using the following command:

```
diagnose cdb check reference-integrity.
```

Example:

```
FMG-VM64 \# diagnose cdb check reference-integrity Checking reference table integrity \dots correct
```


Reviewing FortiManager System Settings

Before starting an upgrade, go to System Settings to review the following widgets:

- · License Information widget
- · System Resources widget to check for high memory and CPU usage

It is also recommended to check the Alert Message Console and the list of notifications.

Following is an example of the *System Settings Dashboard* with the *License Information* and *System Resources* widgets:



Following is an example of the Notification list:



Backing up configuration files and databases

Back up the FortiManager configuration file and databases.

It is recommended that you create a system backup file and save this configuration to your local computer. The device configuration file is saved with a .dat extension.

It is also recommended that you verify the integrity of your backup file.



When the database is larger than 2.8 GB, back up the configuration file to an FTP, SFTP, or SCP server using the following CLI command:

execute backup all-settings {ftp | sftp} <ip> <path/filename of
 server> <username on server> <password> <crptpasswd>
execute backup all-settings scp <ip> <path/filename of server> <SSH
 certificate> <crptpasswd>

For more information, see the FortiManager CLI Reference.

To verify the integrity of a backup file:

- 1. Go to System Settings > Dashboard.
- 2. In the System Information widget, click Backup. The Backup dialog box opens.
- 3. In the Encryption line, deselect the checkbox so that the backup is not encrypted.
- **4.** Click *OK* and save the backup file on your local computer.
- 5. Locate the backup file and change the file extension from .dat to .tgz.
- **6.** Decompress the backup file and verify that the decompression is successful.

If the decompression fails, then the backup process has likely also failed.

To back up your system configuration:

- 1. Go to System Settings > Dashboard.
- 2. In the System Information widget, click Backup. The Backup dialog box opens.
- 3. If you wish, select the checkbox to encrypt the backup file, and enter a password.
- 4. Click OK and save the backup file on your local computer.



If you encrypt the backup file, you must use the same password to restore this backup file.

Creating a snapshot of VM instances

In VM environments, it is recommended to stop the VM instance and take a snapshot or clone of the VM instance before the upgrade. If there are issues with the upgrade, you can revert to the VM snapshot or clone.



Avoid taking snapshots when applications in the virtual machine are communicating with other computers.

Before upgrading a FortiManager VM, upgrade your VM server to the latest stable update and patch release offered by the VM host server provider.

Upgrading FortiManager

You can upgrade FortiManager 5.6.0 or later to FortiManager 6.0.12.

For other upgrade paths, see FortiManager Firmware Upgrade Paths on page 24.

For information about FortiManager support for FortiOS, see the FortiManager Compatibility chart in the Document Library.

This section contains the following topics:

- Upgrading FortiManager Firmware on page 17
- Upgrading the firmware for an operating cluster on page 18
- · Checking FortiManager log output on page 19
- · Checking FortiManager events on page 19
- · Downgrading to previous firmware versions on page 20



When upgrading firmware, all ADOMs (and Policy Package Versions, if ADOMs are disabled) remain at the same version after the upgrade. For information about upgrading ADOMs, see the *FortiManager Administration Guide*.



Upgrading the device firmware can trigger an SQL database rebuild. New logs are not available until the rebuild is complete. The time required to rebuild the database depends on the size of the database. You can use the <code>diagnose sql status rebuild-db</code> command to display the SQL log database rebuild status.

The following features are available until the SQL database rebuild is complete: FortiView, Log View, Event Management, and Reports.

Upgrading FortiManager Firmware

This section describes how to upgrade FortiManager firmware.



Fortinet recommends uploading firmware to FortiManager by using a server that is in the same location as the FortiManager. This helps avoid timeouts.

To upgrade firmware:

- **1.** In *System Settings > Advanced > Advanced Settings*, enable *Offline Mode*. Offline mode stops automatic firmware updates during the upgrade.
- 2. Go to System Settings > Dashboard.
- 3. In the System Information widget, go to the Firmware Version field, and click the Upgrade Firmware icon.

- 4. In the Firmware Upload dialog box, click Browse to locate the firmware package (.out file) that you downloaded from the Customer Service & Support portal, and click Open.
- 5. Click OK.

The firmware image is uploaded. When the upgrade completes, a message confirms a successful upgrade. It is recommended to view the console log output during upgrade. See Checking FortiManager log output on page 19.

6. When the login window displays, log into FortiManager.



When the upgrade completes, you might have to refresh your web browser to see the login window

- 7. In System Settings > Advanced > Advanced Settings, disable Offline Mode.
- 8. Review the System Settings > Event Log for any additional errors. See Checking FortiManager events on page 19.



Optionally, you can upgrade firmware stored on an FTP or TFTP server using the following CLI command:

execute restore image {ftp | tftp} <file path to server> <IP of
 server> <username on server> <password>

For more information, see the FortiManager CLI Reference.

Upgrading the firmware for an operating cluster

You can upgrade the firmware of an operating cluster using the GUI or CLI of the primary unit.

Similar to upgrading the firmware of a standalone unit, normal operations are temporarily interrupted during the cluster firmware upgrade. Therefore, you should upgrade the firmware during a maintenance window.

To upgrade an HA cluster:

- 1. Log into the GUI of the primary unit using the admin administrator account.
- 2. Upgrade the primary unit firmware. The upgrade is automatically synchronized between the primary device and backup devices.

It is recommended to view the console log output during upgrade. See Checking FortiManager log output on page 19.



Administrators may not be able to connect to the GUI until the upgrade synchronization process is completed. During the upgrade, SSH or telnet connections to the CLI may also be slow. You can still use the console to connect to the CLI of the primary device.

Checking FortiManager log output

While upgrading a FortiManager unit, use the console to check the log output in real-time. Check for any errors or warnings.

Following is a sample console output with warnings or errors you might encounter during an upgrade:

```
Please stand by while rebooting the system.
Restarting system.
Serial number: FMG-VM0A11000137
Upgrading sample reports...Done.
Upgrading geography IP data...Done.
rebuilding log database (log storage upgrade)...
Prepare log data for SQL database rebuild...Done.
Global DB running version is 222, built-in DB schema version is 432
upgrading device ssl-vpn flags...done
upgrading scripts ...
Invalid schedule. The device 10160520 does not belong to script 136's adom
Invalid schedule. The device 33933609 does not belong to script 46's adom
Invalid schedule. The device 10515974 does not belong to script 46's adom
Invalid schedule. The device 1709397 does not belong to script 46's adom
Invalid schedule. The device 1709397 does not belong to script 46's adom
Invalid schedule. The device 1407292 does not belong to script 46's adom
upgrading scripts ... done
upgrading script log ...
Failed to upgrade some script logs. Please use "diagnose debug backup-oldformat-script-logs"
     to upload the failed logs into a ftp server
upgrading script log ... done
Upgrading adom vpn certificate ca ...
Finish check-upgrade-objects [32923/49325]
Upgrade all DB version ...
Global DB running version is upgraded to 432
Database upgrade finished, using 846mlls
```

Checking FortiManager events

After upgrading, it is recommended to check all messages logged to the FortiManager Event Log. If you find any errors, you can fix the errors before continuing.

Following is an example of messages in the FortiManager Event Log:



Downgrading to previous firmware versions

FortiManager does not provide a full downgrade path. You can downgrade to a previous firmware release using the GUI or CLI, but this causes configuration loss. A system reset is required after the firmware downgrade. To reset the system, use the following CLI commands via a console port connection:

```
execute reset {all-settings | all-except-ip}
execute format {disk | disk-ext4 | disk-ext3}
```

Verifying FortiManager Upgrade Success

Once the upgrade is complete, check the FortiManager unit to ensure that the upgrade was successful. This section describes items you should check.

This section contains the following topics:

- Checking Alert Message Console and notifications on page 21
- · Checking managed devices on page 21
- Previewing changes for a policy package installation on page 22

Checking Alert Message Console and notifications

After the FortiManager upgrade completes, check the *Alert Message Console* and list of notifications for any messages that might indicate problems with the upgrade.

- In System Settings > Dashboard, check the Alert Message Console widget.
- · Click the Notification icon and review any notifications.

For information on accessing system settings, see Reviewing FortiManager System Settings on page 15.

Checking managed devices

After the FortiManager upgrade completes, check the managed devices in the GUI.

To check managed devices:

- 1. Refresh the browser and log back into the device GUI.
- 2. Go to *Device Manager*, and ensure that all formerly added devices are still listed.
- 3. In *Device Manager*, select each ADOM and ensure that managed devices reflect the appropriate connectivity state. Following is an example of the quick status bar in *Device Manager* where you can check the connectivity status of managed devices. It might take some time for FortiManager to establish connectivity after the upgrade.



4. Launch other functional modules and make sure they work properly. See Previewing changes for a policy package installation on page 22.

Previewing changes for a policy package installation

The first time that you install a policy package after the upgrade, use the Install Preview feature to ensure that only the desired changes will be installed to the device.



The policy package must include a change to use the Install Preview feature.

Following is an example of the Install Preview pane:



Supported Models

FortiManager version 6.0.12 supports the following models:

FortiManager	FortiManager VM
FMG-200D	FMG-VM64
FMG-200F	FMG-VM64-Ali
FMG-300D	FMG-VM64-AWS
FMG-300E	FMG-VM64-AWS-OnDemand
FMG-300F	FMG-VM64-Azure
FMG-400E	FMG-VM64-GCP
FMG-1000D	FMG-VM64-HV (including Hyper-V 2016)
FMG-1000F	FMG-VM64-KVM
FMG-2000E	FMG-VM64-MFGD
FMG-3000F	FMG-VM64-OPC
FMG-3700F	FMG-VM64-XEN (for both Citrix and Open Source Xen)
FMG-3900E	
FMG-4000D	
FMG-4000E	

FortiManager Firmware Upgrade Paths

For information about FortiManager support for FortiOS, see the FortiManager Compatibility chart in the Document Library.

Before upgrading your device, see details in the applicable releases notes.



See Supported Models on page 23 for the list of models that are supported in FortiManager 6.0.12.

Supported models for previous versions can be found in the FortiManager Release Notes for that version.

Firmware Version	Build Number	Upgrade From
6.0.12	0485	6.0.0-6.0.11 5.6.0-5.6.11
Note : FortiManager 6.0.12 does not support ADOM version 5.0. FortiManager 6.0.12 supports only ADOM versions 5.2, 5.4, 5.6, and 6.0.		
6.0.11	0478	6.0.0-6.0.10 5.6.0-5.6.11
6.0.10	0475	6.0.0-6.0.9 5.6.0-5.6.11
6.0.9	0457	6.0.0-6.0.8 5.6.0-5.6.11
6.0.8	0429	6.0.0-6.0.7 5.6.0-5.6.11
6.0.7	0405	6.0.0-6.0.6 5.6.0-5.6.11
6.0.6	0349	6.0.0-6.0.5 5.6.0-5.6.11
6.0.5	0346	6.0.0-6.0.4 5.6.0-5.6.11
6.0.4	0292	6.0.0-6.0.3 5.6.0-5.6.11
6.0.3	0255	6.0.0-6.0.2 5.6.0-5.6.11
6.0.2	0205	6.0.0-6.0.1 5.6.0-5.6.11

Firmware Version	Build Number	Upgrade From
6.0.1	0150	6.0.0 5.6.0-5.6.4 Note : Upgrade from 5.6.5 and later to 6.0.1 is not supported. You must upgrade from 5.6.4 and earlier.
6.0.0	0092	5.6.0-5.6.4 Note : Upgrade from 5.6.5 and later to 6.0.0 is not supported. You must upgrade from 5.6.4 and earlier.
5.6.11	1821	5.6.0-5.6.10 5.4.0-5.4.7
5.6.10	1819	5.6.0-5.6.9 5.4.0-5.4.7
5.6.9	1803	5.6.0-5.6.8 5.4.0-5.4.7
5.6.8	1800	5.6.0-5.6.7 5.4.0-5.4.7
5.6.7	1782	5.6.0-5.6.6 5.4.0-5.4.7
5.6.6	1750	5.6.0-5.6.5 5.4.0-5.4.7
5.6.5	1707	5.6.0-5.6.4 5.4.0-5.4.7
5.6.4	1678	5.6.0-5.6.3 5.4.0-5.4.7
5.6.3	1662	5.6.0-5.6.2 5.4.0-5.4.7
5.6.2	1631	5.6.0-5.6.1 5.4.0-5.4.7
5.6.1	1619	5.6.0 5.4.0–5.4.7
5.6.0	1557	5.4.0-5.4.7



In FortiManager 5.0 and later, FortiClient endpoint agent configuration and management are handled by FortiGate Endpoint Control. You can configure your FortiGate to discover new devices on your network, enforce FortiClient registration, and deploy a pre-configured endpoint profile to connected devices. This feature requires a FortiGate running FortiOS version 5.0 or later.

For more information, see the *Device and Client Reputation for FortiOS 5.0 Handbook* in the Fortinet Document Library.

FortiManager 5.0 and later uses a new hard disk drive partition layout. After upgrading from pre-version 5.0 to 5.0 or later, you must make a backup and then reformat the disk with this command:



execute format {disk | disk-ext4 | disk-ext3}

Formatting the disk erases all local logs and FortiGuard database information. Back up any local event logs you wish to keep. The device will have to re-download all the AV/IPS/AS/WF objects from the FortiGuard Distribution Servers (FDS). This download might take up to half a day. During that time, managed devices cannot obtain these services from FortiManager, so during this time, configure devices to point to a backup FortiManager or the FDS for these services.

Change Log

Date	Change Description
2023-06-08	Initial release.





Copyright© 2023 Fortinet, Inc. All rights reserved. Fortinet®, FortiCare® and FortiGuard®, and certain other marks are registered trademarks of Fortinet, Inc., in the U.S. and other jurisdictions, and other Fortinet names herein may also be registered and/or common law trademarks of Fortinet. All other product or company names may be trademarks of their respective owners. Performance and other metrics contained herein were attained in internal lab tests under ideal conditions, and actual performance and other results may vary. Network variables, different network environments and other conditions may affect performance results. Nothing herein represents any binding commitment by Fortinet, and Fortinet disclaims all warranties, whether express or implied, except to the extent Fortinet enters a binding written contract, signed by Fortinet's General Counsel, with a purchaser that expressly warrants that the identified product will perform according to certain expressly-identified performance metrics and, in such event, only the specific performance metrics expressly identified in such binding written contract shall be binding on Fortinet. For absolute clarity, any such warranty will be limited to performance in the same ideal conditions as in Fortinet's internal lab tests. In no event does Fortinet make any commitment related to future deliverables, features or development, and circumstances may change such that any forward-looking statements herein are not accurate. Fortinet disclaims in full any covenants, representations, and guarantees pursuant hereto, whether express or implied. Fortinet reserves the right to change, modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.