



FortiSandbox - CLI Reference Guide

Version 3.0.0

FORTINET DOCUMENT LIBRARY

<https://docs.fortinet.com>

FORTINET VIDEO GUIDE

<https://video.fortinet.com>

FORTINET BLOG

<https://blog.fortinet.com>

CUSTOMER SERVICE & SUPPORT

<https://support.fortinet.com>

FORTINET COOKBOOK

<https://cookbook.fortinet.com>

FORTINET TRAINING & CERTIFICATION PROGRAM

<https://www.fortinet.com/support-and-training/training.html>

NSE INSTITUTE

<https://training.fortinet.com>

FORTIGUARD CENTER

<https://fortiguard.com/>

END USER LICENSE AGREEMENT

<https://www.fortinet.com/doc/legal/EULA.pdf>

FEEDBACK

Email: techdocs@fortinet.com



July 31, 2018

FortiSandbox 3.0.0 CLI Reference Guide

34-300-495247-20180731

TABLE OF CONTENTS

Change Log	4
Introduction	5
What's New in FortiSandbox	6
Configuration Commands	7
System Commands	8
fw-upgrade	10
pending-jobs	11
device-authorization	12
iptables	13
usg-license	14
hc-settings	15
confirm-id	16
vm-customized	16
sandboxing-cache	17
sandboxing-prefilter	18
sandboxing-embeddedurl	19
filesize-limit	19
remote-auth-timeout	19
log-dropped	20
vm-internet	20
raid-rebuild	21
reset-sandbox-engine	21
set-maintainer	21
set-tlsver	22
fortimail-expired	22
oftpd-con-mode	23
device-lenc	23
upload-license	24
Utility Commands	25
Diagnose Commands	26
diagnose-debug	26
diagnose-sys-top	27

Change Log

Date	Change Description
2018-07-31	Initial release.

Introduction

The FortiSandbox Command Line Interface (CLI) is accessed when connecting to the FortiSandbox via console or using an SSH or TELNET client. These services must be enabled on the port1 interface.

The CLI commands are intended to be used for initial device configuration and troubleshooting. Some commands are specific to hardware or VM devices. Use `?` or `help` with system commands for information on how to use the command.

An administrator's privilege to execute CLI commands is defined by their admin profile. When creating or editing a profile, if the *JSON API / CLI* option is enabled then all CLI commands can be executed by administrators using that profile. If it is disabled, only a limited subset of CLI commands is available.



The FortiSandbox CLI is case-sensitive.

What's New in FortiSandbox

The following tables list the commands and variables that have changed in version 3.0.0.

Command	Description
<code>device-lenc</code>	Enable/disable OFTPD supporting FG-LENC devices.
<code>diagnose-debug adapter_bcc</code>	View debug logs of the BCC adapter in run time.
<code>hc-settings -sd</code>	Disable traffic encryption between HA cluster members.
<code>hc-settings -se</code>	Enable traffic encryption between HA cluster members.
<code>sandboxing-prefiltering</code>	The <code>trustdomain</code> parameter is added in <code>sandboxing-prefiltering</code> . If enabled, the internal white domain list will be used. It is enabled by default.
<code>set port3-speed [<auto> <speed full half>]</code>	Set port3 speed and duplex settings. Not available for FSA-VM model.
<code>set port-mtu <portx> <1500-9000></code>	Set port's MTU value. Not available for FSA-VM model.
<code>set admin-port [port other than port3]</code>	Enable a new administrative port beside port1. It cannot be set on port3 or sniffing ports.

Configuration Commands

The following configuration commands are available:

Command	Description
show	Show the bootstrap configuration, including the port IP address (IPv4 and IPv6), network mask, port MAC address, and default gateway. If the port is being used by a sniffer, it will not be displayed.
set	Set configuration parameters. <ul style="list-style-type: none">• <code>set portX-ip <ip/netmask></code> - Set the portX IP address in IP/netmask format.• <code>set port3-speed [<auto> <speed full half>]</code> - Set port3 speed and duplex settings.• <code>set port-mtu <portx> <1500-9000></code> - Set a port's MTU value. Not available for FSA-VM model.• <code>set admin-port <portx></code> - Enable a new administrative port other than port1. It cannot be set to port3 or sniffer ports.• <code>set default-gw <ip></code> - Set the default gateway address.• <code>set date <date></code> - Set system date, in the format of YYYY-MM-DD.• <code>set time <time></code> - Set system time, in the format of HH:MM:SS.
unset	Unset the admin port or the default gateway: <ul style="list-style-type: none">• <code>unset admin-port</code>• <code>unset default-gw</code>

System Commands

Command	Description
<code>reboot</code>	Reboot the FortiSandbox. All sessions will be terminated. The unit will go offline and there will be a delay while it restarts.
<code>config-reset</code>	Reset the FortiSandbox configuration to factory default settings. Job data will be kept. For installed VM images, their clone numbers and <i>Scan Profile</i> settings are set back to default.
<code>factory-reset</code>	Reset the FortiSandbox configuration to factory default settings. All data are deleted. For installed VM images, only Default VMs are kept and their clone number and <i>Scan Profile</i> settings are set to default values.
<code>shutdown</code>	Shutdown the FortiSandbox.
<code>status</code>	Display the FortiSandbox firmware version, serial number, system time, disk usage, image status check, Microsoft Windows VM status, VM network access configuration, and RAID information.
<code>sandbox-engines</code>	Display FortiSandbox FortiGuard component versions including the Tracer Engine, Rating Engine, Traffic Sniffer, Botnet Signature Database, IPS Signature Database, and Android engine versions.
<code>vm-license -l</code>	List embedded Windows Product key information.
<code>vm-status</code>	Show VM system status and their license situation. If there is an issue with a VM, an error message will be displayed with information to help troubleshoot the problem.
<code>vm-reset</code>	Activate and initialize a VM image again. Sometimes it is necessary to rebuild a VM image when it is broken. Optionally, specify a VM name with <code>-n <VM name></code> , or all VMs will be reset.
<code>fw-upgrade</code>	Upgrade or re-install the FortiSandbox firmware via Secure Copy (SCP) or File Transfer Protocol (FTP) server. See fw-upgrade on page 10 for details.
<code>reset-widgets</code>	Reset the GUI widgets.
<code>cleandb</code>	Clean up the internal database and job information. This command will erase all stored data and reboot the device.
<code>log-purge</code>	Delete all system logs.
<code>pending-jobs</code>	Show the status of or delete pending jobs. See pending-jobs on page 11 for details.

Command	Description
device- authorization	Configure new client device authorization . See device-authorization on page 12 for details.
iptables	Enable/disable IP tables. See iptables on page 13 for details.
usg-license	Convert the unit to be USG licensed. See usg-license on page 14 for details.
hc-settings	Configure the unit as a HA-Cluster mode unit. See hc-settings on page 15 for details.
hc-status -l	List the status of HA-Cluster units.
hc-slave	Add/update/remove a slave unit to/from an HA-Cluster. This command can only be run on a slave unit.
hc-master	Enable/disable the malware detection features on master unit. Use <code>-s<percent></code> to turn on file scan and set the percentage of the scanning capacity to be used. If no number is entered, 50% will be used.
confirm-id	Set confirm ID for Microsoft Windows or Office activation. See confirm-id on page 16 for details.
vm-customized	Install customized VM. See vm-customized on page 16 for details.
sandboxing-cache	Enable/disable sandboxing result check. See sandboxing-cache on page 17 for details.
reset-scan-profile	Reset the clone number and file extension association back to firmware default values using the <code>-r</code> option.
sandboxing- prefilter	Enable/disable sandboxing prefilter for file types. See sandboxing-prefilter on page 18 for details.
sandboxing- embeddedurl	Enable/disable feature for sandboxing embedded urls in PDF or OFFICE documents. See sandboxing-embeddedurl on page 19 for details.
filesize-limit	Set file size limitation for scan input type, in megabytes (default = 200). See filesize-limit on page 19 for details.
remote-auth- timeout	Set the timeout for remote authentication. See remote-auth-timeout on page 19 for details.
log-dropped	Enable/disable the log file drop event. See log-dropped on page 20 for details.

Command	Description
<code>vm-internet</code>	Allow Virtual Machines to access external network through outgoing port3 and set gateway for port3. See vm-internet on page 20 for details.
<code>cm-status -l</code>	List the status of units joining the Global Threat Information Network.
<code>raid-rebuild</code>	Rebuild raid after a new HD replaces a bad one. See raid-rebuild on page 21 for details.
<code>reset-sandbox-engine</code>	Reset the tracer/rating engine back to firmware default. See reset-sandbox-engine on page 21 for details.
<code>set-maintainer</code>	Enable/disable the maintainer account. See set-maintainer on page 21 for details.
<code>set-tlsver</code>	Set the allowed TLS version for HTTPS service. See set-tlsver on page 22 for details.
<code>fortimail-expired</code>	Enable/disable expired timeout option for FortiMail files. See fortimail-expired on page 22 for details.
<code>oftpd-con-mode</code>	Enable/disable conserve mode of OFTPD. See oftpd-con-mode on page 23 for details.
<code>device-lenc</code>	Enable/disable OFTPD supporting FortiGate-LENC devices. See device-lenc on page 23 for details.
<code>resize-hd</code>	After changing the virtual hard disk size on the hypervisor, execute this command to make the change recognizable to the firmware. This command is only available for FSA_VM-Base and FSAVM00 models.
<code>upload license</code>	Download firmware license file from a server and install it. See upload-license on page 24 for details.

fw-upgrade

Upgrade or re-install the FortiSandbox firmware via SCP or FTP server. Before running this option, the firmware file should be downloaded to a server that supports file copy via FTP/SCP.

The system will boot up after the firmware is downloaded and installed.

Syntax

```
fw-upgrade <option> [options]
```

Option	Description
-h	Help information.
-b	Download an image file from this server and upgrade the firmware.
-v	Download a VM image file from this server and install.
-t<ftp scp>	The protocol type, FTP or SCP (default =SCP).
-s<IP address>	The IP address of the server that the image will be downloaded from.
-u<user name>	The user name for authentication.
-p<password>	The password for authentication.
-f<file path>	The full path for the image file.

pending-jobs

This command allows users to view job queues statistics and purge them.

Syntax

```
pending-jobs <show|purge> <source> <filetype>
```

Option	Description
show / purge	Show or purge the pending jobs.
source	<p>One of:</p> <ul style="list-style-type: none"> all ondemand rpc device sniffer adapter netshare url - URLs submitted through the On Demand page. urlrpc - URLs submitted through JSON API. urldev - URLs submitted from devices such as FortiMail. urladapter urlsniffer - URLs embedded in email body that are detected by sniffer.

Option	Description
filetype	<p>One of:</p> <ul style="list-style-type: none"> • all • exe • pdf • doc • flash • web • url • android • mac • user • notset - Jobs that will not be scanned by guest image. • waiting - Files have not been processed to enter the job queue.

device-authorization

Users can decide to either manually or automatically authorize a new client device.

Syntax

```
device-authorization <option>
```

Option	Description
-h	Help information.
-a	When a new device other than FortiClient registers, FortiSandbox will authorize it automatically.
-m	When a new device other than FortiClient registers, the user has to authorize it manually from the GUI.
-e	Authorize all existing devices if they are not already.
-o	When a new FortiClient registers, it inherits authorization status from the managing EMS or FortiGate. or the user has to change it manually from the GUI.
-f	When a new FortiClient registers, FortiSandbox will authorize it automatically.
-l	Display the status of device and FortiClient authorization (default = manual).

iptables

This command is used to enable or disable IP tables. The settings will be discarded after reboot.

Syntax

```
iptables -[ACD] chain rule-specification [options]
iptables -I chain [rulenum] rule-specification [options]
iptables -R chain rulenum rule-specification [options]
iptables -D chain rulenum [options]
iptables -[LS] [chain [rulenum]] [options]
iptables -[FZ] [chain] [options]
iptables -[NX] chain
iptables -E old-chain-name new-chain-name
iptables -P chain target [options]
iptables -h (print this help information)
```

Commands

Either long or short commands are allowed.

<code>--append -A chain</code>	Append to chain.
<code>--check -C chain</code>	Check for the existence of a rule.
<code>--delete -D chain</code>	Delete matching rule from chain.
<code>--delete -D chain rulenum</code>	Delete rule rulenum (1 = first) from chain.
<code>--insert -I chain [rulenum]</code>	Insert in chain as rulenum (default 1=first).
<code>--replace -R chain rulenum</code>	Replace rule rulenum (1 = first) in chain.
<code>--list -L [chain [rulenum]]</code>	List the rules in a chain or all chains.
<code>--list-rules -S [chain [rulenum]]</code>	Print the rules in a chain or all chains.
<code>--flush -F [chain]</code>	Delete all rules in chain or all chains.
<code>--zero -Z [chain [rulenum]]</code>	Zero counters in chain or all chains.
<code>--new -N chain</code>	Create a new user-defined chain.
<code>--delete-chain -X [chain]</code>	Delete a user-defined chain.
<code>--policy -P chain target</code>	Change policy on chain to target.
<code>--rename-chain -E old- chain new-chain</code>	Change chain name, (moving any references).

Options

Either long or short options are allowed.

<code>--ipv4 -4</code>	Nothing (line is ignored by <code>ip6tables-restore</code>).
<code>--ipv6 -6</code>	Error (line is ignored by <code>iptables-restore</code>).
<code>[!] --protocol -p proto</code>	Protocol: by number or name, for example: <code>tcp</code> .
<code>[!] --source -s address [/mask] [...]</code>	Source specification.
<code>[!] --destination -d address[/mask] [...]</code>	Destination specification.
<code>[!] --in-interface -i input name[+]</code>	Network interface name ([+] for wildcard).
<code>--jump -j target</code>	Target for rule (may load target extension).
<code>--goto -g chain</code>	Jump to chain with no return.
<code>--match -m match</code>	Extended match (may load extension).
<code>--numeric -n numeric</code>	Output of addresses and ports.
<code>[!] --out-interface -o output name[+]</code>	Network interface name ([+] for wildcard).
<code>--table -t table</code>	Table to manipulate (default: <code>'filter'</code>).
<code>--verbose -v</code>	Verbose mode.
<code>--wait -w</code>	Wait for the <code>xtables</code> lock.
<code>--line-numbers</code>	Print line numbers when listing.
<code>--exact -x</code>	Expand numbers (display exact values).
<code>[!] --fragment -f</code>	Match second or further fragments only.
<code>--modprobe=<command></code>	Try to insert modules using this command.
<code>--set-counters PKTS BYTES</code>	Set the counter during insert/append.
<code>[!] --version -V</code>	Print package version.

usg-license

Convert the unit to be USG licensed. When a USG license is applied, only FortiGuard Distribution Network (FDN) servers in the United States can be used.

syntax

```
usg-license
```

Option	Description
-h	Help information.
-l	List the USG license status.
-s<USG-license-string>	Set this unit to be USG licensed.
-r<Regular-license-string>	Revert the unit back to a regular license.

hc-settings

Configure the unit as a HA-Cluster mode unit.

syntax

```
hc-settings <option> [option] [options]
```

Option	Description
-h	Help information.
-l	List the Cluster configuration.
-sc	Set this unit to be a HA-Cluster mode unit.
-t<N M P R>	Set this unit to be a HA-Cluster mode unit.
N	N/A.
M	Master unit.
P	Primary slave unit.
R	Regular slave unit.
-n<name string>	Set alias name for this unit.
-c<HA-CLUSTER name>	Set the HA-Cluster name for master unit.
-p<authentication code>	Set the authentication code for master unit.
-i<interface>	Set interface used for cluster internal communication.
-si	Set the fail-over IPs for this cluster for master unit.

Option	Description
-i<interface>	Specify the interface for external communication
-a<IP/netmask>	Specify the IP address and netmask for external communication. This IP address will be applied as the alias IP of the specified interface. It must be in the same subnet as the unit IP subnet of the specified interface.
-se	Enable traffic encryption between HA cluster members.
-sd	Disable traffic encryption between HA cluster members.

confirm-id

Validate a Microsoft Windows or Office key after contacting Microsoft customer support. For more details, please contact [Fortinet Customer Support](#).

Syntax

```
confirm-id <option> [options]
```

Option	Description
-a	Add a confirmation ID
-k	License key.
-c	Conformation ID.
-d	Delete a confirmation ID.
-k	License key.
-l	List all confirmation IDs.

vm-customized

Install a customized VM.

Syntax

```
confirm-id <option> ... <option>
```


Option	Description
-h	Help information.
-c[n l f d]	Operation command.
n	Install a new customized VM.
l	List installed customized VM.
f	Upload a meta file for a customized VM.
d	Display a meta file for a customized VM.
-t<ftp scp>	The protocol type, FTP or SCP (default = scp).
-s<server IP>	Download the image file from this FTP or SCP server IP address.
-u<user name>	The user name for authentication.
-p<password>	The password for authentication.
-f<full path of filename>	The full path for the image file or meta file.
-d<hardware/machine ID>	The original hardware ID or machine ID.
-k<MD5 checksum>	The MD5 checksum for the uploaded file.
-v[o n]	Set the base information for VM image
-o<OS type>	WindowsXP, Windows7, Windows7_64, Windows81, Windows81_64 , Windows10, or Windows10_64.
-n<VM name>	The name of the VM.
-r <VM name>	Replace the VM if it already exists.
-m <VM meta file name>	The name of the VM meta file.

sandboxing-cache

Turn on or off the sandboxing result cache.

When it is off, the same file will be scanned again by sandboxing. When it is on, sandboxing scan results will be added to an internal cache and reused in future when the same file is scanned.

When the scan condition is changed, such as when a new tracer engine is installed, the cache will be purged.

Syntax

```
sandboxing-cache <option>
```

Option	Description
-h	Help information.
-e	Enable sandboxing result cache.
-d	Disable sandboxing result cache.
-l	Display the status of sandboxing result cache.
-r	Remove all existing cache results

sandboxing-prefilter

Allow user to turn on or off FortiGuard prefiltering of certain file types.

If a file type is associated with a guest VM image, it will be scanned if the file type enters the job queue as defined in the Scan Profile page. The user can turn on FortiGuard prefiltering of a file type so that files of that type will first be statically scanned by an advanced analytic engine, and only suspicious files will be sandboxing scanned by the guest image. This can improve the system's scan performance, and all files will still go through an AV scan, a static scan, and community cloud query steps.

For the URL type, when FortiGuard prefiltering is enabled, only URLs whose web filtering rating is Unrated will be scanned inside associated guest VM image.

Syntax

```
sandboxing-prefilter [-h|-l|-e|-d] -t[dll|pdf|swf|js|htm|url|office|trustvendor|trustdomain]
```

Option	Description
-h	Help information.
-e	Enable sandboxing prefilter.
-d	Disable sandboxing prefilter.
-l	Display the status of sandboxing prefilter.
-t	Enable/disable sandboxing prefilter for specific file types: <code>dll</code> , <code>pdf</code> , <code>swf</code> , <code>js</code> , <code>htm</code> , <code>url</code> , <code>office</code> , <code>trustvendor</code> , <code>trustdomain</code> . When <code>trustvendor</code> is selected, executable files from a small internal list of trusted vendors will skip the sandboxing scan step. When <code>trustdomain</code> is selected, files downloaded from a small internal list of trusted domains will skip the sandboxing scan step

sandboxing-embeddedurl

Turn on or off sandboxing embedded URLs in PDF or Office documents. Only randomly selected URLs will be scanned.

Syntax

```
sandboxing-cache <option>
```

Option	Description
-h	Help information.
-e	Enable sandboxing embedded URLs in PDF or Office documents.
-d	Disable status for sandboxing embedded URLs.
-i	Disable embedded URL extraction in PDF or Office documents.
-l	Display the status of sandboxing embedded URL.

filesize-limit

Set file size limit of different input sources.

Syntax

```
filesize-limit [-h|-l|-t] -t[all|ondemand|netshare|jsonrpc|icap|device] -v[MB]
```

Option	Description
-h	Help information.
-l	Display the file size limitation.
-t	Set the input sources: all, ondemand, netshare, and/or jsonrpc.
-v	Set the file size limitation, in megabytes (0 - 1024, default = 200).

remote-auth-timeout

Set Radius or LDAP authentication timeout value.

Syntax

```
remote-auth-timeout <option>
```

Option	Description
-h	Help information.
-s	Set the timeout value, in seconds (10 - 180, default = 10).
-u	Unset the timeout value.
-l	Display the timeout value.

log-dropped

Enable/disable the log file drop event.

Syntax

```
log-dropped [-h|-l|-e|-d]
```

Option	Description
-h	Help information.
-l	Show the current configuration.
-e	Enable log dropped file.
-d	Disable log dropped file.

vm-internet

Syntax

```
vm-internet [options]
```

Option	Description
-h	Help information.
-l	Display the current configuration.
-s	Set the VM internet configuration for port3.
-g<gateway IP>	Next hop gateway IP address.
-d<DNS server IP>	DNS server IP address.
-u	Unset VM internet configuration for port3.

raid-rebuild

Rebuild raid after a new HD replaces a bad one.

Syntax

```
raid-rebuild <options>
```

Option	Description
-h	Help information.
-d[<i>diskno</i>]	Rebuild RAID after the HD disk number is swapped.
-l[<i>diskno</i>]	Show the rebuild progress.

reset-sandbox-engine

Reset tracer and rating engines back to firmware default.

Syntax

```
reset-sandbox-engine <option>
```

Option	Description
-h	Help information.
-t	Reset tracer engine to firmware default.
-r	Reset rating engine to firmware default.
-b	Reset both tracer and rating engines to firmware default.

set-maintainer

The maintainer account is used to reset users' passwords.

Syntax

```
set-maintainer <option>
```

Option	Description
-h	Help information.
-l	Show current setting.
-d	Disable maintainer account.
-e	Enable maintainer account.

set-tlsver

Set allowed TLS version for HTTPS service.

Syntax

```
set-tlsver <option>
```

Option	Description
-h	Help information.
-l	Show current TLS versions.
-r	Reset to default versions.
-e	Set the allowed TLS versions. 1 and 2 are for TLS 1.1 and 1.2 respectively. Separate versions with , for example -e1 2 will enable TLS 1.1 and 1.2. TLSv1.0 is not supported.

fortimail-expired

Enable/disable timeout check for FortiMail files. By default, FortiMail will hold mail for set period to wait for the verdict from FortiSandbox. Before FortiSandbox scans a file or URL that is sent from FortiMail, it will check if the verdict is still needed - FortiMail may have already released the email after timeout. If not, FortiSandbox will give the job an *Other* rating and a *skipped* status.

Syntax

```
fortimail-expired <option>
```

Option	Description
-h	Help information.

Option	Description
-e	Enable expired timeout for FortiMail files.
-d	Disable expired timeout for FortiMail files.
-l	Display the status of timeout feature for FortiMail files.

oftpd-con-mode

Enable/disable conserve mode of OFTPD.

Syntax

```
oftpd-con-mode <option>
```

Option	Description
-h	Help information.
-e	Enable OFTPD conserve mode.
-d	Disable OFTPD conserve mode.
-l	Display the status of OFTPD conserve mode.

device-lenc

Enable/disable OFTPD supporting FG-LENC devices.

Syntax

```
device-lenc <option>
```

Option	Description
-h	Help information.
-e	Enable support for Low-Encryption (LENC) devices.
-d	Disable support for Low-Encryption (LENC) devices.
-l	Display current support status for Low-Encryption (LENC) devices.

upload-license

Download firmware license file from a remote server and install it.

This command is only available for FSA_VM-Base and FSAVM00 models.

Syntax

```
upload_license <options>
```

Option	Description
-s<server ip>	Download a license file from this server IP address.
-t<ftp scp>	The protocol type, FTP or SCP (default =SCP).
-u<username>	The user name for server authentication.
-p<password>	The password for server authentication.
-f<license filename>	The full path for the license file.

Utility Commands

The following utilities are available:

Command	Description
ping	Test network connectivity to another network host: <code>ping <IP address></code>
tcpdump	Examine local network traffic: <code>tcpdump [-c count] [-i interface] [expression]</code>
tracert	Examine the route taken to another network host: <code>tracert <host></code>

Diagnose Commands

The following diagnostic commands are available:

Command	Description
<code>hardware-info</code>	Display general hardware status information. Use this option to view CPU, memory, disk, and RAID information, as well as system time settings.
<code>diagnose-debug</code>	Display detailed debug logs of network share scan and communications with devices. See diagnose-debug on page 26 for details.
<code>diagnose-sys-top</code>	Display system top information. See diagnose-sys-top on page 27 for details.
<code>diagnose-sys-perf</code>	Display system performance information. Optionally, specify how many previous hours to show with <code>-m<hours></code> (maximum = 40320, default = 1).
<code>disk-attributes</code>	Display system disk attributes. This option is only available on hardware models.
<code>disk-errors</code>	Display any system disk errors. This option is only available on hardware models.
<code>disk-health</code>	Display disk health information. This option is only available on hardware models.
<code>disk-info</code>	Display disk hardware status information. This option is only available on hardware models.
<code>raid-hwinfo</code>	Display RAID hardware status information. This option is only available on hardware models.
<code>test-network</code>	Test the network connection. The output can be used to detect network speed and connection to FDN servers and Microsoft servers.

diagnose-debug

Display detailed debug logs of network share scan and communications with devices. It is useful for troubleshooting OFTP and network share scan issues.

Syntax

```
diagnose-debug [netshare|device|adapter] [device_serial_number]
```

Option	Description
netshare	Network share daemon
device	OFTP daemon for FortiGate, FortiMail, and FortiClient devices.
adapter_cb	Daemon for third party device such as Bit9 + CARBON BLACK.
adapter_icap	Daemon for Internet Content Adaptation Protocol (ICAP).
adapter_bcc	Daemon for BCC.
device_serial_number	The device serial number.

diagnose-sys-top

Display current system top processes and current CPU and memory usage.


Syntax

```
diag-sys-top -[h|l|i|]
```

Option	Description
-h	Help information.
-l<value>	Maximum lines (maximum = 100, default = 50).
-i<value>	Interval to delay, in seconds (default = 5).
Keyboard input operations:	
q	or ^C quit.
m	Sort by memory usage.
p	Sort by CPU usage
t	Sort by time usage.
n	Sort by PID



FORTINET®



Copyright© 2018 Fortinet, Inc. All rights reserved. Fortinet®, FortiGate®, FortiCare® and FortiGuard®, and certain other marks are registered trademarks of Fortinet, Inc., in the U.S. and other jurisdictions, and other Fortinet names herein may also be registered and/or common law trademarks of Fortinet. All other product or company names may be trademarks of their respective owners. Performance and other metrics contained herein were attained in internal lab tests under ideal conditions, and actual performance and other results may vary. Network variables, different network environments and other conditions may affect performance results. Nothing herein represents any binding commitment by Fortinet, and Fortinet disclaims all warranties, whether express or implied, except to the extent Fortinet enters a binding written contract, signed by Fortinet's General Counsel, with a purchaser that expressly warrants that the identified product will perform according to certain expressly-identified performance metrics and, in such event, only the specific performance metrics expressly identified in such binding written contract shall be binding on Fortinet. For absolute clarity, any such warranty will be limited to performance in the same ideal conditions as in Fortinet's internal lab tests. In no event does Fortinet make any commitment related to future deliverables, features or development, and circumstances may change such that any forward-looking statements herein are not accurate. Fortinet disclaims in full any covenants, representations, and guarantees pursuant hereto, whether express or implied. Fortinet reserves the right to change, modify, transfer, or otherwise revise this publication without notice, and the most current version of the publication shall be applicable.